

->enable
->config
->create client-username user1-fin message-vpn myservice
->create client-username user1-fin message-vpn myservice
->create client-username user1-fin message-vpn myservice
->client-profile default
->guaranteed-endpoint-permission-override
->no shutdown

```
mr-connection-gi45bp3bocp.messaging.solace.cloud - PuTTY
Keyboard-interactive authentication prompts from server:
| Password:
| End of keyboard-interactive prompts from server

Solace PubSub+ Enterprise Version 10.4.1.59

This Solace product is proprietary software of
Solace Corporation. By accessing this Solace product
you are agreeing to the license terms and conditions
located at http://www.solace.com/license-software

Copyright 2004-2023 Solace Corporation. All rights reserved.

Operating Mode: Message Routing Node

developer-production-9f12f3i2ulk-solace-primary-0> enable
developer-production-9f12f3i2ulk-solace-primary-0# config
developer-production-9f12f3i2ulk-solace-primary-0(configure)# create client-username user1-fin message-vpn myservice
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)# create client-username user2-fin message
-vpn myservice

Invalid command input
  create client-username user2-fin message-vpn myservice
    ^
-> unknown command, or command not available in current mode
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)# exit
developer-production-9f12f3i2ulk-solace-primary-0(configure)# create client-username user2-fin message-vpn myservice
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)# exit
developer-production-9f12f3i2ulk-solace-primary-0(configure)# client-username user1-fin message-vpn myservice
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)# client-profile default
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)# guaranteed-endpoint-permission-override
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)# no shutdown
developer-production-9f12f3i2ulk-solace-primary-0(configure/client-username)#
```