

# 贪吃蛇环境准备

## 一、gcc 环境搭建：


- 1、拷贝 gcc 软件到 c 盘下
- 2、添加环境变量（添加 C:\mingw64\bin 至）




计算器——>属性，找到高级系统设置，单击。



单击环境变量



找到系统变量中的 Path，双击。



单击【新建】，添加 gcc 的 bin 路径到空格处。

## 3、环境验证

在命令提示符中输入 `gcc -v`，出现以下界面，说明环境配置成功！

```
命令提示符
target: x86_64-w64-mingw32
Configured with: ../../src/gcc-8.1.0/configure --host=x86_64-w64-mingw32 --build=x86_64-w64-mingw32 --target=x86_64-w64-mingw32 --prefix=/mingw64 --with-sysroot=/c/mingw810/x86_64-810-posix-sjlj-rt_v6-rev0/mingw64 --enable-shared --enable-static --enable-targets=all --enable-multilib --enable-languages=c,c++,fortran,lto --enable-libstdcxx-time=yes --enable-threads=posix --enable-libgomp --enable-libatomic --enable-lto --enable-graphite --enable-checking=release --enable-fu
lly-dynamic-string --enable-version-specific-runtime-libs --enable-sjlj-exceptions --disable-libstdcxx-pch --disable-libstdcxx-debug --enable-bootstrap --disable-rpath --disable-win32-registry --disable-nls --disable-werror --disable-symver
s --with-gnu-as --with-gnu-ld --with-arch=32-i686 --with-arch=64-nocona --with-tune=32-generic --with-tune=64-core2 --wi
th-libiconv --with-system-zlib --with-gmp=/c/mingw810/prerequisites/x86_64-w64-mingw32-static --with-mpfr=/c/mingw810/prerequisites/x86_64-w64-mingw32-static --with-mpc=/c/mingw810/prerequisites/x86_64-w64-mingw32-static --with-isl=/c/mingw810/prerequisites/x86_64-w64-mingw32-static --with-pkgversion=x86_64-posix-sjlj-rev0, Built by MinGW-W64 project --with-bugurl=https://sourceforge.net/projects/mingw-w64 CFLAGS='-O2 -pipe -fno-ident -I/c/mingw810/x86_64-810-posix-sjlj-rt_v6-rev0/mingw64/opt/include -I/c/mingw810/prerequisites/x86_64-zlib-static/include -I/c/mingw810/prerequisites/x86_64-w64-mingw32-static/include' CXXFLAGS='-O2 -pipe -fno-ident -I/c/mingw810/x86_64-810-posix-sjlj-rt_v6-rev0/mingw64/opt/include -I/c/mingw810/prerequisites/x86_64-zlib-static/include -I/c/mingw810/prerequisites/x86_64-w64-mingw32-static/include' CPPFLAGS='-I/c/mingw810/x86_64-810-posix-sjlj-rt_v6-rev0/mingw64/opt/include -I/c/mingw810/prerequisites/x86_64-zlib-static/include -I/c/mingw810/prerequisites/x86_64-w64-mingw32-static/include' LDFLAGS='-pipe -fno-ident -L/c/mingw810/x86_64-810-posix-sjlj-rt_v6-rev0/mingw64/opt/lib -L/c/mingw810/prerequisites/x86_64-zlib-static/lib -L/c/mingw810/prerequisites/x86_64-w64-mingw32-static/lib'
Thread model: posix
gcc version 8.1.0 (x86_64-posix-sjlj-rev0, Built by MinGW-W64 project)

C:\Users\huawei>
```