


## REFERENCE GUIDE

# Knowledge Base Template



# Contents

Introduction .....	3
Changing Home Page Tiles .....	4
Changing Variables .....	8

# Introduction

Welcome to the *Knowledge Base Template Reference Guide*. This guide outlines quick custom changes that can be made to the template to fit your brand. For more details about Flare and implementing features into your project, please refer to the online Help at <https://help.madcapsoftware.com>.

You should have already branded the project for your company via the Start a New Project Wizard. This lets you choose your company colors, font, logo, and hero image. You can always update these by opening the Content Explorer and navigating to **Resources > Branding > Branding.css**.

# Changing Home Page Tiles

The tiles on the Home page have a height value of **250px**. In order to change these settings, you must edit the **Styles.css** file.

These are the  
"Home Tiles."




FictionSoft Knowledge Base is used for any information related to all released versions of FictionSoft Product 1.




Need help getting your project configured?  
Contact [MadCap Software Technical Support](#).

# How to Change the Home Page Tiles


1. Open the Content Explorer, expand **Resources > Stylesheets**, and double-click **Styles.css**.




2. In the Stylesheet Editor, make sure you are in **Advanced** view.




3. On the left side, expand **(Complex Selectors)** and select **div.home-tiles > div**.



4. On the right side of the editor, next to **height**, type the new value. You can also click ... and use the dialog.



 **Note:** If you have group view enabled instead of alphabetical view, you will need to expand the **Box** group before making your changes.



**Note:** If you remove the height property, the tiles will automatically resize based on the contents.

5. Save the file.


# Changing Variables

You might use variables for company information, social media URLs, product names, the date of publication, and more. To change the definitions for the variables used in this template, edit the **General** variable set file. You can also create and insert new variables for other purposes.



# How to Change Variables

1. Open the Project Organizer, expand **Variables**, and double-click **General**.



2. In the Variable Set Editor, click twice slowly in the **Definition** cell you want to change and type the new text.

The screenshot shows the 'Variable Set Editor' window with the 'General' tab selected. The table below lists variables and their definitions. A red arrow points to the 'Definition' cell for 'CompanyName'.

Name	Definition
CityStateZip	La Jolla, CA
CompanyName	FictionSoft
Email	info@yourcompany.com
Facebook	http://www.facebook.com/madcapdocteam
PhoneNumber	858 123 4567
Product 1	Product 1
Product 2	Product 2
Product 3	Product 3
StreetAddress	1234 Lorem Ipsum Ave.
Twitter	https://twitter.com/#!/MadCapDocTeam
Updated	MMMM dd, yyyy
Year	yyyy

3. Press **Enter** on your keyboard.

4. Repeat these steps for each variable definition you want to change. (You can also use the buttons in the local toolbar to add new variables if you like.)
5. Save the file. When you open a file where a variable has been inserted (e.g., Home.htm), you should see the new definition(s) displayed.