

DEVICE	Credentials	INTERFACE	INTERFACE CONNECTED TO	NETWORK	IPv4 ADDRESS(static)
HQ-EDGE-ASA-FW	local admin: username hq-admin password	G0/0	HQ	10.0.1.0/30	10.0.1.1/30
HQ-EDGE-ASA-FW	local viewer: username supportro password	G0/1	TERRY-ISP	198.51.100.224/30	198.51.100.226/30
HQ-EDGE-ASA-FW	enable secret hq-p@ssw0rd encrypted (hq-p@ssw0rd)	Loop0		2.2.2.2/32	2.2.2.2/32
HQ-EDGE-ASA-FW		Tunnel10(enterpri	VTI	172.16.10.0/30	172.16.10.1/30
HQ-EDGE-ASA-FW		Tunnel20(enterpri	VTI	172.16.20.0/30	172.16.20.1/30
BRANCH-1-EDGE-ASA-FW	local admin: username branch1-admin password	G0/0	TERRY-ISP	203.0.113.48/30	203.0.113.50/30
BRANCH-1-EDGE-ASA-FW	local viewer: username supportro password	G0/1	BRANCH-1	10.0.2.0/30	10.0.2.1/30
BRANCH-1-EDGE-ASA-FW	enable secret: branch-1-edge	Loop0		6.6.6.6/32	6.6.6.6/32
BRANCH-1-EDGE-ASA-FW		Tunnel10(enterpri	VTI	172.16.10.0/30	172.16.10.2/30
BRANCH-2-EDGE-ASA-FW	local admin: username branch2-admin password	G0/0	TERRY-ISP	192.0.2.144/30	192.0.2.146/30
BRANCH-2-EDGE-ASA-FW	local viewer: username supportro password	G0/1	BRANCH-2	10.0.3.0/30	10.0.3.1/30
BRANCH-2-EDGE-ASA-FW	enable secret: branch-2-edge	Loop0		7.7.7.7/32	7.7.7.7/32
BRANCH-2-EDGE-ASA-FW		Tunnel20(enterpri	VTI	172.16.20.0/30	172.16.20.2/30
TERRY-ISP		G0/0	HQ-EDGE-ASA-FW	198.51.100.224/30	198.51.100.225/30
TERRY-ISP		G0/1	BRANCH-2-EDGE-ASA-FW	192.0.2.144/30	192.0.2.145/30
TERRY-ISP		G0/2	BRANCH-1-EDGE-ASA-FW	203.0.113.48/30	203.0.113.49/30
TERRY-ISP		Loop0		1.1.1.1/32	1.1.1.1/32
HQ		G0/0	HQ-SW-1	10.0.1.4/30	10.0.1.5/30
HQ		G0/1	HQ-SW-2	10.0.1.8/30	10.0.1.9/30
HQ		G0/2	HQ-EDGE-ASA-FW	10.0.1.0/30	10.0.1.2/30
HQ		Loop0		10.0.1.64/26	10.0.1.66/32
HQ		Loop1		5.5.5.5/32	5.5.5.5/32
BRANCH-1		G0/0	BRANCH-1-EDGE-ASA-FW	10.0.2.0/30	10.0.2.2/30
BRANCH-1		G0/1	BRANCH-1-SW	10.0.2.4/30	10.0.2.5/30
BRANCH-1		Loop0		10.0.2.64/26	10.0.2.66/32
BRANCH-1		Loop1		3.3.3.3/32	3.3.3.3/32
BRANCH-2		G0/0	BRANCH-2-EDGE-ASA-FW	10.0.3.0/30	10.0.3.2/30
BRANCH-2		G0/1	BRANCH-2-SW	10.0.3.4/30	10.0.3.5/30
BRANCH-2		Loop0		10.0.3.64/26	10.0.3.66/32
BRANCH-2		Loop1		4.4.4.4/32	4.4.4.4/32
HQ-SW-1		G0/0	HQ	10.0.1.4/30	10.0.1.6/30
HQ-SW-1		Po1	HQ-SW-2	10.0.1.12/30	10.0.1.13/30
HQ-SW-2		G0/0	HQ	10.0.1.8/30	10.0.1.10/30
HQ-SW-2		Po1	HQ-SW-1	10.0.1.12/30	10.0.1.14/30
BRANCH-1-SW		G0/0	BRANCH-1	10.0.2.4/30	10.0.2.6/30
BRANCH-2-SW		G0/0	BRANCH-2	10.0.3.4/30	10.0.3.6/30
VLAN 10 (PCs) HQ				10.0.1.128/25	10.0.1.129/25
VLAN 10 (PCs) HQ				10.0.1.128/25	10.0.1.130/25
VLAN 10 (PCs) BRANCH1				10.0.2.128/25	10.0.2.129/25
VLAN 10 (PCs) BRANCH2				10.0.3.128/25	10.0.3.129/25
VLAN 99 (Management) HQ				10.0.1.64/26	10.0.1.65/26
VLAN 99 (Management) HQ				10.0.1.64/26	10.0.1.67/26
VLAN 99 (Management) BRANCH 1				10.0.2.64/26	10.0.2.65/26
VLAN 99 (Management) BRANCH 2				10.0.3.64/26	10.0.3.65/26
Manangement server		g0/0	HQ-SW-1	Layer 2	10.0.1.126/26
RADIUS		eth0	HQ-SW-1	Layer 2	10.0.1.125/26