

```

1      identification          division.
2      program-id.            PW0010.
3      environment             division.
4      configuration           section.
5      input-output            section.
6      file-control.
7
8      *> Cliente
9      copy "/hbsis/selects/arq-cliente.sl"
10     *> Vendedor
11     copy "/hbsis/selects/arq-vendedor.sl"
12     *> Importar Cliente
13     copy "/hbsis/selects/arq-imp-cliente.sl"
14     *> Importar Vendedor
15     copy "/hbsis/selects/arq-imp-vendedor.sl"
16     *=====
17     data                    division.
18     file                    section.
19
20     *> Cliente
21     copy "/hbsis/fds/arq-cliente.fd"
22     *> Vendedor
23     copy "/hbsis/fds/arq-vendedor.fd"
24     *> Importar Cliente
25     copy "/hbsis/fds/arq-imp-cliente.fd"
26     *> Importar Vendedor
27     copy "/hbsis/fds/arq-imp-vendedor.fd"
28
29     *=====
30     working-storage         section.
31     77 wk-separar           pic x(080) value all "EM".
32     77 wk-hifennn           pic x(080) value all "-".
33     77 wk-fstatus          pic x(002) value spaces.
34     77 wk-confirm          pic x(001) value spaces.
35     77 wk-opcao            pic 9(004) value zeros.
36     77 wk-delayss          pic x(001) value spaces.
37     77 wk-arquivo          pic x(006) value spaces.
38
39     01 wk-area.
40         05 work-limpar      PIC X(060) VALUE SPACES.
41
42     *=====
43
44     screen                  section.
45     01 tela-limpa.
46         02 line 14 col 01 pic x(70) using work-limpar.
47         02 line 15 col 01 pic x(70) using work-limpar.
48         02 line 16 col 01 pic x(70) using work-limpar.
49         02 line 17 col 01 pic x(70) using work-limpar.
50         02 line 18 col 01 pic x(70) using work-limpar.
51         02 line 19 col 01 pic x(70) using work-limpar.
52         02 line 20 col 01 pic x(70) using work-limpar.
53         02 line 21 col 01 pic x(70) using work-limpar.
54         02 line 22 col 01 pic x(70) using work-limpar.
55
56     01 tela-01-menu.
57         02 line 1 col 1 reverse-video value "MENU PRINCIPAL".
58         02 line 06 col 22 value "0101 - Cadastro de Clientes" ".
59         02 line 07 col 22 value "0102 - Cadastro de Vendedores" ".
60         02 line 08 col 22 value "0201 - Relatorio de Clientes" ".
61         02 line 09 col 22 value "0202 - Relatorio de Vendedores" ".
62         02 line 10 col 22 value "0301 - Distribuir Clientes X Vendedores" ".
63         02 line 09 col 22 value "9999 - Sair" ".
64         02 col 33 highlight value "digite opcao:".
65         02 col 49 value "_____".
66
67     01 tela-02-cadastro-cliente.
68         02 line 1 col 1 reverse-video value "MENU CADASTRO CLIENTES".
69         02 line 06 col 22 value "0101 - inclusao" ".
70         02 line 07 col 22 value "0102 - alteracao" ".
71         02 line 08 col 22 value "0103 - exclusao".
72         02 line 08 col 22 value "0104 - importar".

```

```

72         02 col 33 highlight value "digite opcao:".
73         02 col 49 value "_____".
74
75     01 tela-02-cadastro-vendedor.
76         02 line 1 col 1 reverse-video value "MENU CADASTRO VENDEDORES".
77         02 line 06 col 22 value "0101 - inclusao".
78         02 line 07 col 22 value "0102 - alteracao".
79         02 line 08 col 22 value "0103 - exclusao".
80         02 line 08 col 22 value "0104 - importar".
81         02 col 33 highlight value "digite opcao:".
82         02 col 49 value "_____".
83
84     01 tela-02-cad-vend-inc.
85         02 line 1 col 1 reverse-video value "CADASTRO VENDEDORES".
86         02 line 05 col 22 value "codigo vendedor: ".
87         02 col 32 value "_____".
88         02 line 06 col 22 value "cpf: ".
89         02 col 24 value "_____".
90         02 line 07 col 22 value "nome vendedor:".
91         02 col 49 value "_____".
92         02 line 07 col 22 value "latitude:".
93         02 col 49 value "_____".
94         02 line 07 col 22 value "longitude:".
95         02 col 49 value "_____".
96
97     01 tela-02-cad-cli-inc.
98         02 line 1 col 1 reverse-video value "CADASTRO CLIENTE".
99         02 line 05 col 22 value "codigo cliente: ".
100        02 col 32 value "_____".
101        02 line 06 col 22 value "cnpj: ".
102        02 col 24 value "_____".
103        02 line 07 col 22 value "razao social:".
104        02 col 49 value "_____".
105        02 line 07 col 22 value "latitude:".
106        02 col 49 value "_____".
107        02 line 07 col 22 value "longitude:".
108        02 col 49 value "_____".
109
110    01 tela-03-relatorio-cliente.
111        02 line 1 col 1 reverse-video value "MENU RELATORIO CLIENTE".
112        02 line 07 col 22 value "0101-Lista Clientes - Ordem Ascendente
113
114        02 line 08 col 22 value "0102-Lista Clientes - Ordem Descendente".
115        02 line 08 col 22 value "0103-Filtro porCodigo Cliente".
116        02 line 08 col 22 value "0104-Filtro por Razao Social do Cliente".
117        02 col 33 highlight value "digite opcao:".
118        02 col 49 value "_____".
119
120    01 tela-03-relatorio-vendedor.
121        02 line 1 col 1 reverse-video value "MENU RELATORIO VENDEDORES".
122        02 line 07 col 22 value "0201-Lista Vendedores - Ordem Ascendente
123
124        02 line 08 col 22 value "0202-Lista Vendedores - Ordem Descendente".
125        02 line 08 col 22 value "0203-Filtro porCodigo Vendedor".
126        02 line 08 col 22 value "0204-Filtro por Nome
127
128        Vendedor".
129        02 col 33 highlight value "digite opcao:".
130        02 col 49 value "_____".
131
132    *=====
133    procedure                                division.
134    0000-principal                          section.
135        perform 1000-inicializa
136        perform 2000-processa
137        until wk-opcao equal 9999 or esc
138        perform 3000-finaliza.
139    0000-principal-exit.
140        exit.
141
142    *=====
143    1000-inicializa                          section.
144        display tela-limpa .
145    1000-exit.

```

```

142         exit.
143
144     *=====
145     2000-processa                section.
146         initialize                wk-opcao
147         display tela-01-menu
148         accept  wk-opcao          at 1447 with upper
149                                     auto-skip highlight.
150
151         if esc
152             exit perform;
153         end-if
154
155         evaluate wk-opcao
156             when 0101
157                 perform 2100-cadastro-cliente
158             when 0102
159                 perform 2200-cadastro-vendedor
160             when 0201
161                 perform 2300-relatorio-cliente
162             when 0202
163                 perform 2400-relatorio-vendedor
164             when 0301
165                 perform 2800-distrib-clientes
166             when 9999
167                 exit perform
168         end-evaluate.
169
170     .
171     2000-exit.
172
173     *=====
174     2100-cadastro-cliente        section.
175         initialize wk-opcao
176         display tela-02-cadastro-cliente
177         accept  wk-opcao          at 1447 with upper
178                                     auto-skip highlight.
179
180         if esc
181             exit perform;
182         end-if
183
184         evaluate work-opcao-menu
185             when 0101
186                 perform 2110-cad-inc-cli
187             when 0102
188                 perform 2120-cad-alt-cli
189             when 0103
190                 perform 2130-cad-exc-cli
191             when 0104
192                 perform 2140-cad-importacao
193             when 9999
194                 exit perform
195         end-evaluate
196
197     .
198     2100-exit.
199
200     *=====
201     2110-cad-inc-cli             section.
202
203         display tela-02-cad-cli-inc
204
205         accept rs-cod-cli          at 1534
206         accept rs-cnpj             at 1634
207
208         move    rs-cnpj            to wk-2115-cnpj-cpf
209         move    1                  to wk-2115-tipo-cad
210         perform 2115-consulta-cnpj      *> Consiste
211         if ws-status-arq equal 99
212             exit perform
213         end-if
214
215         accept rs-razao-social      at 1734
216         accept rs-latitude-cli       at 1834
217         accept rs-longitude-cli      at 1934
218
219         open extend arq-cliente
220         if ws-resultado-acesso equal "00"

```

```

215         write arq-cliente from rs-arq-cli
216     end-if
217
218     close arq-cliente
219
220 2110-exit.
221 *=====
222 2115-consulta-cnpj                section.
223
224     if wk-2115-tipo-cad equal 1          *> tipo cliente
225         if wk-2115-cnpj-cpf < 14
226             move 99          to ws-status-arq
227             display "cnpj invalido"
228             exit section
229         end-if
230     end-if
231
232     if wk-2115-tipo-cad equal 2          *> tipo vendedor
233         if wk-2115-cnpj-cpf < 11
234             move 99          to ws-status-arq
235             display "CPF invalido"
236             exit section
237         end-if
238     end-if
239
240     perform until ws-status-arq <> 00
241         read arqclientes next
242         if w-cod-cnpj equal w-reg-cpf-cnpj
243             move 99          ws-status-arq
244             display "ja existe cnpj ou cpf cadastrado!"
245             exit perform
246         end-if
247     end-perform
248
249 2115-exit.
250 *=====
251 2120-cad-alt-cli                section.
252     initialize rs-arq-cli
253
254     open i-o arq-cliente
255     if ws-resultado-acesso equal "00"
256         display "Entre Codigo Cliente para alterar:"
257         accept rs-cod-cli
258         start arq-cliente key is = rs-cod-cli
259         if ws-resultado-acesso equal "00"
260             read arq-cliente
261             display tela-02-cad-cli-inc
262             accept rs-cod-cli          at 1534
263             accept rs-cnpj             at 1634
264             move rs-cnpj              to wk-2115-cnpj-cpf
265             move 1                    to wk-2115-tipo-cad
266             perform 2115-consulta-cnpj          *> Consiste
267             if ws-status-arq equal 99
268                 exit perform
269             end-if
270
271             accept rs-razao-social    at 1734
272             accept rs-latitude-cli     at 1834
273             accept rs-longitude-cli   at 1934
274
275             rewrite arq-cliente from rs-arq-cli
276         end-if
277     end-if
278 2120-exit.
279     exit.
280 *=====
281 2130-cad-exc-cli                section.
282
283     initialize rs-arq-cli
284
285     open i-o arq-cliente
286     if ws-resultado-acesso equal "00"
287         display "Entre Codigo Cliente para excluir:"

```

```

288         accept rs-cod-cli
289
290         start arq-cliente key is = rs-cod-cli
291         if ws-resultado-acesso equal "00"
292             read arq-cliente
293             display tela-02-cad-cli-inc
294
295             display "Deseja Excluir registro (s / n)"
296             accept wk-opcao
297             if wk-opcao equal 'S' or 's'
298                 delete arq-cliente from rs-arq-cli
299                 end-if
300             end-if
301         end-if.
302 2130-exit.
303     exit.
304 *=====
305 2140-cad-importacao          section.
306
307     initialize ws-status-arq
308     display tela-02-importacao
309     accept w-arq-caminho-importar
310
311     if w-arq-caminho-importar is null
312         display "Caminho vazio do arquivo importar"
313         exit perform
314     end-if
315
316     if wk-opcao equal 0104      *> Cliente
317         open i-o arq-cliente
318         open i-o arq-imp-cli
319         if ws-resultado-acesso equal 00 then
320             perform until ws-resultado-acesso not equal zeros
321                 read arq-imp-cli next
322                 move rs-imp-cod-cli          to rs-cod-cli
323                 move rs-imp-cnpj             to rs-cnpj
324                 move rs-imp-razao-social    to
rs-razao-social
325                 move rs-imp-lat-cli          to
rs-latitude-cli
326                 move rs-imp-long-cli         to
rs-longitude-cli
327                 write arq-cliente from rs-arq-cli
328             end-perform
329         end-if
330         close arq-cliente
331         close arq-imp-cli
332         else
333         open i-o arq-vendedor
334         open i-o arq-imp-vend
335         if ws-resultado-acesso equal 00 then
336             perform until ws-resultado-acesso not equal zeros
337                 read arq-imp-vend next
338                 move rs-imp-cod-vend        to rs-cod-vend
339                 move rs-imp-cpf             to rs-cpf
340                 move rs-imp-nome            to rs-nome
341                 move rs-imp-lat-vend        to rs-latitude-vend
342                 move rs-imp-long-vend       to rs-latitude-vend
343                 write arq-vendedor from rs-arq-vend
344             end-perform
345         end-if
346         close arq-vendedor
347         close arq-imp-vend
348     end-if
349 2140-exit.
350     exit.
351 *=====
352 2200-cadastro-vendedor      section.
353     initialize wk-opcao
354     display tela-02-cadastro-vendedor
355     accept wk-opcao          at 1447 with upper
356                               auto-skip highlight.

```

```

358         if esc
359             exit perform;
360         end-if
361
362     evaluate work-opcao-menu
363         when 0101
364             perform 2210-cad-incl-vend
365         when 0102
366             perform 2220-cad-alt-vend
367         when 0103
368             perform 2230-cad-exc-vend
369         when 0104
370             perform 2140-cad-importacao
371         when 9999
372             exit perform
373     end-evaluate
374 2200-exit.
375     exit.
376
377 *=====
378 2210-cad-incl-vend                section.
379
380     display tela-02-cad-vend-inc
381     accept rs-cod-cli              at 1534
382     accept rs-cnpj                 at 1634
383
384     move    rs-cnpj                to wk-2115-cnpj-cpf
385     move    1                      to wk-2115-tipo-cad
386     perform 2115-consulta-cnpj      *> Consiste
387     if ws-status-arq equal 99
388         exit perform
389     end-if
390
391     accept rs-razao-social         at 1734
392     accept rs-latitude-cli          at 1834
393     accept rs-longitude-cli         at 1934
394
395     open extend arq-cliente
396     if ws-resultado-acesso equal "00"
397         write arq-cliente from rs-arq-cli
398     end-if
399
400     close arq-cliente
401
402 2210-exit.
403     exit.
404 *=====
405 2220-cad-alt-vend                section.
406     initialize rs-arq-vend
407     open i-o arq-cliente
408     if ws-resultado-acesso equal "00"
409         display "Entre Codigo Cliente para alterar:"
410         accept rs-cod-cli
411         start arq-cliente key is = rs-cod-cli
412         if ws-resultado-acesso equal "00"
413             read arq-cliente
414             display tela-02-cad-cli-inc
415             accept rs-cod-cli        at 1534
416             accept rs-cnpj           at 1634
417             move    rs-cnpj          to wk-2115-cnpj-cpf
418             move    1                to wk-2115-tipo-cad
419             perform 2115-consulta-cnpj *> Consiste
420             if ws-status-arq equal 99
421                 exit perform
422             end-if
423             accept rs-razao-social  at 1734
424             accept rs-latitude-cli   at 1834
425             accept rs-longitude-cli  at 1934
426
427             rewrite arq-cliente from rs-arq-cli
428         end-if
429     end-if

```

```

430 .
431 2220-exit.
432     exit.
433
434 *=====
435 2230-cad-exc-vend                section.
436
437     initialize rs-arq-cli
438
439     open i-o   arq-cliente
440     if ws-resultado-acesso equal "00"
441         display "Entre Codigo Cliente para excluir:"
442         accept  rs-cod-cli
443
444         start arq-cliente key is = rs-cod-cli
445         if ws-resultado-acesso equal "00"
446             read arq-cliente
447             display tela-02-cad-cli-inc
448
449             display "Deseja Excluir registro (s / n)"
450             accept wk-opcao
451             if wk-opcao equal 'S' or 's'
452                 delete arq-cliente from rs-arq-cli
453             end-if
454         end-if
455     end-if
456 .
457 2230-exit.
458     exit.
459
460 *=====
461 2300-relatorio-cliente          section.
462     initialize                  ws-opcao
463
464     display tela-03-relatorio-cliente
465     accept  ws-opcao
466
467     evaluate ws-opcao
468
469     when 0101
470     when 0102
471         perform 2311-lista-cli-asc-desc
472     when 0103
473         perform 2313-filtro-por-cod-cli
474     when 0104
475         perform 2314-filtro-por-razao
476     end-evaluate.
477
478 2300-exit.
479     exit.
480
481 *=====
482 2311-lista-cli-asc-desc        section.
483     initialize rs-cod-cli
484
485     open input arq-cliente
486     if ws-resultado-acesso equal zeros
487
488         if ws-opcao equal 0101                                *> Ascendente
489             start arq-cliente key is >= rs-cod-cli
490         else
491             initialize rs-cod-cli                                *> Descendente
492             move 9999                                         to rs-cod-cli
493             start arq-cliente key is <= rs-cod-cli
494         end-if
495         display "Codigo;CNPJ;Razao Social;Latitude;Longitude"
496         perform until ws-resultado-acesso not equal zeros
497             read next arq-cliente
498             display rs-arq-cli
499         end-perform
500     end-if
501 2311-exit.
502     exit.

```

```

503 *=====
504 2313-filtro-por-cod-cli
505     display tela-limpa
506
507     open input  arq-clientes
508     if ws-resultado-acesso equal zeros
509         display "Entre Codigo Cliente para filtra relatorio:"
510         accept  rs-cod-cli
511         start  arq-cliente key is = rs-cod-cli
512         read   arq-cliente
513         display rs-arq-cliente
514             close arq-clientes
515     end-if.
516
517 2313-exit.
518     exit.
519
520 *=====
521 2314-filtro-por-razao
522     display tela-limpa
523
524     open input  arq-clientes
525     if ws-resultado-acesso equal zeros
526         display "Entre Razao Social Cliente para filtra relatorio:"
527         accept  rs-razao-social
528
529         start  arq-cliente key is = rs-razao-social
530         read   arq-cliente
531         display rs-arq-cliente
532             close arq-clientes
533     end-if.
534
535 2314-exit.
536     exit.
537
538 *=====
539 2400-relatorio-vendedor      section.
540             initialize                ws-opcao
541
542     display tela-03-relatorio-vendedor
543     accept  ws-opcao
544
545             evaluate ws-opcao
546     when 0201
547     when 0202
548         perform 2422-lista-vend-asc-desc
549     when 0203
550         perform 2423-filtro-por-cod-vend
551     when 0204
552         perform 2424-filtro-por-nome
553     end-evaluate.
554 2400-exit.
555     exit.
556
557 *=====
558 2422-lista-vend-asc-desc      section.
559     initialize rs-arq-vend
560
561     open input  arq-vendedor
562     if ws-resultado-acesso equal zeros
563         if ws-opcao equal 0101                *> Ascendente
564             start arq-cliente key is >= rs-cod-vend
565         else                *> Descendente
566             move 9999                to rs-cod-vend
567             start arq-cliente key is <= rs-cod-vend
568         end-if
569         display "Codigo;CPF;NOME;Latitude;Longitude"
570         perform until ws-resultado-acesso not equal zeros
571             read next arq-vendedor
572             display rs-arq-vend
573         end-perform
574     end-if
575 2422-exit.

```



```

576         exit.
577
578 *=====
579 2423-filtro-por-cod-vend      section.
580     display tela-limpa
581
582     open input  arq-vendedor
583     if ws-resultado-acesso equal zeros
584         display "Entre Codigo Vendedor para filtra relatorio:"
585         accept  rs-cod-vend
586         start  arq-vendedor key is = rs-cod-vend
587         read   arq-vendedor
588         display rs-arq-vendedor
589             close arq-vendedor
590     end-if.
591 2423-exit.
592     exit.
593
594 *=====
595 2424-filtro-por-razao
596     display tela-limpa
597     open input  arq-vendedor
598     if ws-resultado-acesso equal zeros
599         display "Entre Nome Vendedor para filtra relatorio:"
600         accept  rs-nome
601         start  arq-vendedor key is = rs-nome
602         read   arq-vendedor
603         display rs-arq-vendedor
604             close arq-vendedor
605     end-if.
606 2424-exit.
607     exit.
608
609 *=====
610 2800-distrib-clientes      section.
611             move      work-nomearq      to lk-caminho.
612     move      zeros      to lk-regfunc.
613     call      "/hbsis/modulo/pw00900" using lk-rot405.
614     cancel    "pw00900".
615 2800-exit.
616     exit.
617
618 *=====
619 3000-finaliza      section.
620     exit      program
621     stop      run
622     .
623 3000-exit.
624     exit.

```