

Visualiser Documentation

Ruben Saunders

November 2024

Contents

1	Overview	2
1.1	Command-Line Interface	2
1.2	Execution Example	2
2	Main – Code Execution	2
2.1	Layout	2
2.2	Keyboard Controls	3

1 Overview

The visualiser offers an interactive view into code execution and the interaction between the compiler, the assembler, and the processor. The visualiser

- Is machine-code executor, able to run the loaded binary on the processor in a step-wise fashion.
- Has a register view/editor.
- Has a memory view/editor.
- Is a basic debugger.
- Shows the current machine-code instruction, and back-traces it to both the assembly and high-level source code.

The application is a TUI (a textual user interface), meaning it runs in the terminal. The interface is tab-based, with a navigation bar along the top. Later sections will cover the content of each tab.

1.1 Command-Line Interface

The visualiser executable is called as follows:

```
1 $ ./visualiser --asm <asm_file> --bin <bin_file>
```

The `--asm` and `--bin` flags set the source assembly and binary files, respectively. The file provided to `--asm` is the output from the assembler's reconstruction; if not, features such as trace-back will not be enabled.

1.2 Execution Example

The visualiser relies on output from the assembler. Below is the sequence of steps to go from a source assembly file, to running it on the visualiser.

1. Write an assembly source, say `source.asm`.
2. Assemble the file, emitting a reconstruction.

```
1 $ ./assembler source.asm -o source -r source.s
```

3. Launch the visualiser.

```
1 $ ./visualiser --asm source.s --bin source
```

2 Main – Code Execution

The “main” tab, this view shows the source and compiler assembly side-by-side.

2.1 Layout

The top of the screen is split into two panes.

- The assembly source is displayed on the left, with its file name displayed.
- The reconstructed compiler assembly is display on the right.

The current line pointed to by `$pc` is highlighted in yellow, which is traced back to the source assembly. If enabled, the currently selected line is displayed in cyan, with the corresponding equivalent lines highlighted in light cyan in the other pane.

Below this is a section for the processor's debug messages, which is hidden by default unless messages are available. The fields below this display the

- Processor's status – either *halted* or *running*. This reflects the `is_running` bit in `$flag`.
- Cycle – indicates the processor's current cycle, i.e., number of executed steps.
- Program counter – the current value of `$pc`.

2.2 Keyboard Controls

- **End** – if line selection is enabled, set the selected line to the end of the file.
- **Enter** – if the processor is running, perform a step on the processor, i.e., execute the instruction at `$pc`.
- **Home** – if line selection is enabled, set the selected line to the start of the file.
- **j** – if line selection is enabled, sets `$pc` to the first selected line in the compiled assembly.
- **r** – resets `$flag`: sets `is_running` and clears any error bits.
- **s** – toggle line selection.
- **Up/Down arrows** – if line selection is enabled, moves the active selected line (cyan) up/down in the current file.
- **Left/Right arrows** – if line selection is enabled, scrolls through the current panes. The active selected line (cyan) is transferred to the topmost selected line in the new pane.