




These are the three audio volume controls.

Use the fader gain to see which one's on, then realign all using the volume control.

Select "Speakers (Sound Blaster Audigy 5/Rx)" in Windows sound settings:




Using the external app “Voicemeeter Windows Volume” app, bind Win vol ctrl to all three outputs:



Individual speaker settings:

System > Sound > Properties

**left LC27T55**
NVIDIA High Definition Audio
[Rename](#)

Provider

NVIDIA

Driver date

1/19/2023

Driver version

1.3.40.14

Check for driver updates

General

Audio

Allow apps and Windows to use this device for audio

Don't allow

Set as default sound device

Not used as a default

Output settings

Format

Test

24 bit, 48000 Hz (Studio Quality)

Volume

23

Left channel

23

Right channel

23

Audio enhancements

Select an enhancement available for your device

Device Default Effects

Microsoft Audio Home Theater Effects


Author: NVIDIA

Spatial sound

Choose an immersive audio experience that simulates a realistic environment (3D Spatial Sound)

Dolby Atmos for Headphones

System > Sound > Properties

**right LC27T55**
NVIDIA High Definition Audio
[Rename](#)

Provider

NVIDIA

Driver date

1/19/2023

Driver version

1.3.40.14

Check for driver updates

General

Audio

Allow apps and Windows to use this device for audio

Don't allow

Set as default sound device

Not used as a default

Output settings

Format

Test

24 bit, 48000 Hz (Studio Quality)

Volume

64

Left channel

64

Right channel

64

Audio enhancements

Select an enhancement available for your device

Device Default Effects

Microsoft Audio Home Theater Effects


Author: NVIDIA

Spatial sound

Choose an immersive audio experience that simulates a realistic environment (3D Spatial Sound)

Dolby Atmos for Headphones

System > Sound > Properties

**SPDIF Out**
Sound Blaster Audigy 5/Rx
[Rename](#)

Provider

Creative Technology, Ltd.

Driver date

8/14/2018

Driver version

6.0.301.56

[Check for driver updates](#)

General

Audio

Allow apps and Windows to use this device for audio

Don't allow

Set as default sound device

Not used as a default

Output settings

Format

Test

2 channels, 16 bit, 48000 Hz (DVD Quality)

Volume


32

Left channel

32

Right channel

32


 Spatial sound

Choose an immersive audio experience that simulates a realistic environment (3D Spatial Sound)

[Get more spatial sound apps from Microsoft Store](#)

Dolby Atmos for Headphones

When in doubt, uninstall the drivers for the monitors and check for changes, reinstall:



You can also use the external application to restart the audio engine or Voicemeeter itself.

