

ADDRESS TABLE

DEVICE	INTERFACE	ADDRESS IPV4	VLAN	DEFAULT GW	VRF	INTERFACE DESCRIPTION	LOCATION	OS image
Site1	ens34	192.168.1.2/24	N/A	192.168.1.1	N/A	Site1 to CE1 or CE11, Interface Management	CUSTOMER HQ LAN	ubuntu-18.04.1.0-live-server-amd64.iso
CE1	FastEthernet0/0	192.168.1.1/24	N/A	N/A	N/A	CE1 to Site1, Default Gw	CUSTOMER HQ LAN	c7200-advipservicesk9-mz.152-4.S5.image
	GigabitEthernet3/0	209.165.1.1/30	N/A	N/A	N/A	CE1 to PE1		
	Loopback0	6.6.6.6/32	N/A	N/A	N/A	Test interface		
	Tunnel1	10.10.10.1/30	N/A	N/A	N/A	CE1 to CE2		
CE11	GigabitEthernet0/0	192.168.1.1/24	N/A	N/A	N/A	CE11 to Site1, Default Gw	CUSTOMER HQ LAN	vios-adventerprise9-m
	GigabitEthernet0/2	209.165.1.1/30	N/A	N/A	N/A	CE11 to PE1		
	Loopback0	5.5.5.5/32	N/A	N/A	NA	Test interface		
PE1	GigabitEthernet0/0	209.165.1.2/30	N/A	N/A	CLEAR	PE1 to CE11	PROVIDER LAN	vios-adventerprise9-m
	GigabitEthernet0/1	192.168.1.1/30	N/A	N/A	N/A	PE1 to P		
	GigabitEthernet0/2	209.165.1.2/30	N/A	N/A	HIDDEN	PE1 to CE1		
	Loopback0	1.1.1.1/24	N/A	N/A	N/A	For MPLS Process		
P	GigabitEthernet0/1	192.168.1.2/30	N/A	N/A	N/A	P to PE1	PROVIDER LAN	vios-adventerprise9-m
	GigabitEthernet0/2	192.168.2.1/30	N/A	N/A	N/A	P to PE2		
	Loopback0	2.2.2.2/24	N/A	N/A	N/A	For MPLS Process		
PE2	GigabitEthernet0/0	209.165.2.1/30	N/A	N/A	CLEAR	PE2 to CE22	PROVIER LAN	vios-adventerprise9-m
	GigabitEthernet0/1	209.165.2.1/30	N/A	N/A	HIDDEN	PE2 to CE2		
	GigabitEthernet0/2	192.168.2.2/30	N/A	N/A	N/A	PE to P		
	Loopback0	3.3.3.3/24	N/A	N/A	N/A	For MPLS Process		
CE22	GigabitEthernet0/0	192.168.2.1/24	N/A	N/A	N/A	CE22 to Site2	CUSTOMER	vios-adventerprise9-m

				GigabitEthernet0/1	209.165.2.2/30	N/A	N/A	N/A	CE22 to PE2	BRANCH LAN			
				Loopback0	4.4.4.4/32	N/A	N/A	N/A	Test Interface				
				CE2	FastEthernet0/0	192.168.2.1/24	N/A	N/A	N/A	CE2 to Site2, Default Gw	CUSTOMER BRANCH LAN	c7200-advipservicesk9 -mz.152-4.S5.image	
					GigabitEthernet3/0	209.165.2.2/30	N/A	N/A	N/A	CE2 to PE2			
					Loopback0	7.7.7.7/32	N/A	N/A	N/A	Test interface			
					Tunnel1	10.10.10.2/30	N/A	N/A	N/A	CE2 to CE1			
				Site2	ens34	192.168.2.2/24	N/A	192.168.2.1	N/A	Site2 to CE2 or CE22, Interface Management	CUSTOMER BRANCH LAN	ubuntu-18.04.1.0- live-server-amd64.iso	
				server1	eth0	10.10.1.1/24		1	N/A	N/A	LAN Default GW	CUSTOMER HQ LAN	gns3/ipterm
					eth1	10.10.0.1/30	N/A		10.10.0.2	N/A	WAN Interface		
				server2	eth0	10.10.2.1/24		12	N/A	N/A	LAN Default GW	CUSTOMER HQ LAN	gns3/ipterm
					eth1	10.10.0.2/30	N/A		10.10.0.1	N/A	WAN Interface		
				pc1	eth0	10.10.1.2/24		1	10.10.1.1	N/A	LAN Interface	CUSTOMER BRANCH LAN	gns3/ipterm
				pc2	eth0	10.10.1.3/24		1	10.10.1.1	N/A	LAN Interface	CUSTOMER BRANCH LAN	gns3/ipterm
				pc3	eth0	10.10.2.2/24		2	10.10.2.1	N/A	LAN Interface	CUSTOMER BRANCH LAN	gns3/ipterm
				pc4	eth0	10.10.2.3/24		2	10.10.2.1	N/A	LAN Interface	CUSTOMER BRANCH LAN	gns3/ipterm