




# Запрегалов Николай ИС 221



The configuration window for Router0 is open, showing the CLI interface. The configuration commands entered are:

```
Router>en
Router#conf
Configuring from terminal, memory, or network [terminal]? t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#fa0/0
% Invalid input detected at '^' marker.
Router(config)#int fa0/0
Router(config-if)#ip address 192.168.0.4
Router(config-if)#ip address 192.168.0.4 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-6-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#ip
```



Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x: 1284, y: 321

Printer-PT Printer0

PC-PT PC0

Time: 00:25:44

Server0

Physical Config Services Desktop Programming Attributes

SERVICES

- HTTP
- DHCP
- DHCPv6
- TFTP
- DNS
- SYSLOG
- AAA
- NTP
- EMAIL
- FTP
- IoT
- VM Management
- Radius EAP

DNS

DNS Service ☒ On ☐ Off

Resource Records

Name  Type A Record

Address

Add Save Remove

No.	Name	Type	Detail
0	frunze86	A Record	192.168.0.5

DNS Cache

Root

Realtime Simulation

Type Color Time(sec) Periodic Num Edit

ENG 8:46

Cisco Packet Tracer

File Edit Options View Tools Extensions Window Help

Logical Physical x: 1158, y: 184

Printer-PT Printer0

PC-PT PC0

Time: 00:26:35

Printer0

Physical Config Attributes

GLOBAL

Settings

INTERFACE

FastEthernet0

Port Status ☒ On

Bandwidth ☒ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 0060.3E4A.D930

IP Configuration

☐ DHCP

☒ Static

IPv4 Address 192.168.0.6

Subnet Mask 255.255.255.0

IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

Link Local Address FE80::260:3EFF:FE4A:D930

Root

Realtime Simulation

Type Color Time(sec) Periodic Num Edit

ENG 8:46

