

enable
Config

Create client-username cu07 message-vpn change-message-vpn

Enter into existing client user

client-username cu06 message-vpn change-message-vpn
acl-profile <name>

client-profile<name>
Guaranteed-endpoint-permission-override

Subscription-manager
(No shutdown to enable) but to change acl profile it need to disabled

```
Copyright 2004-2023 Solace Corporation. All rights reserved.

Operating Mode: Message Routing Node

developer-production-69xlr5fp56g-solace-primary-0> en
developer-production-69xlr5fp56g-solace-primary-0# con
developer-production-69xlr5fp56g-solace-primary-0(configure)# Create client-user
name cu06 message-vpn change-message-vpn
ERROR: Cannot create client-username 'cu06': already exists
Command Failed

developer-production-69xlr5fp56g-solace-primary-0(configure)# Create client-user
name cu06 message-vpn change-message-vpn
ERROR: Cannot create client-username 'cu06': already exists
Command Failed

developer-production-69xlr5fp56g-solace-primary-0(configure)# Create client-user
name cu07 message-vpn change-message-vpn
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# ex
it
developer-production-69xlr5fp56g-solace-primary-0(configure)# client-username c
u07 message-vpn change-message-vpn
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)#
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# ac
```

```
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# cl
ient-profile default
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# Gu
aranteed-endpoint-permission-override
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# no
Guaranteed-endpoint-permission-override
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# Su
bscription-manager
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# no
Subscription-manager
developer-production-69xlr5fp56g-solace-primary-0(configure/client-username)# ??
```

Commands available in the current mode:

[no] acl-profile

[create|no] attribute

- The ACL Profile of the Client Username.
- Create, modify, or delete a Client Username Attribute.

A ClientUsername Attribute is a key+value pair that can be used to locate a client