

tf.contrib.rnn.DeviceWrapper

Contents

Class DeviceWrapper

Aliases:

Properties

activity_regularizer

Class DeviceWrapper

Inherits From: [RNNCell](#)

Aliases:

- Class `tf.contrib.rnn.DeviceWrapper`
- Class `tf.nn.rnn_cell.DeviceWrapper`

Defined in [tensorflow/python/ops/rnn_cell_impl.py](#).

See the guide: [RNN and Cells \(contrib\) > Core RNN Cell wrappers \(RNNCells that wrap other RNNCells\)](#)

Operator that ensures an RNNCell runs on a particular device.

Properties

activity_regularizer

Optional regularizer function for the output of this layer.

dtype

graph

input

Retrieves the input tensor(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer.

Returns:

Input tensor or list of input tensors.

Raises:

- `AttributeError` : if the layer is connected to more than one incoming layers.

Raises:

- `RuntimeError` : If called in Eager mode.
- `AttributeError` : If no inbound nodes are found.

input_shape

Retrieves the input shape(s) of a layer.

Only applicable if the layer has exactly one input, i.e. if it is connected to one incoming layer, or if all inputs have the same shape.

Returns:

Input shape, as an integer shape tuple (or list of shape tuples, one tuple per input tensor).

Raises:

- `AttributeError` : if the layer has no defined input_shape.
- `RuntimeError` : if called in Eager mode.

losses

name

non_trainable_variables

non_trainable_weights

output

Retrieves the output tensor(s) of a layer.

Only applicable if the layer has exactly one output, i.e. if it is connected to one incoming layer.

Returns:

Output tensor or list of output tensors.

Raises:

- `AttributeError` : if the layer is connected to more than one incoming layers.
- `RuntimeError` : if called in Eager mode.

output_shape

Retrieves the output shape(s) of a layer.

Only applicable if the layer has one output, or if all outputs have the same shape.

Returns:

Output shape, as an integer shape tuple (or list of shape tuples, one tuple per output tensor).

Raises:

- `AttributeError` : if the layer has no defined output shape.
- `RuntimeError` : if called in Eager mode.

output_size

scope_name

state_size

trainable_variables

trainable_weights

updates

variables

Returns the list of all layer variables/weights.

Returns:

A list of variables.

weights

Returns the list of all layer variables/weights.

Returns:

A list of variables.

Methods

`__init__`

```
__init__(  
    cell,  
    device  
)
```

Construct a `DeviceWrapper` for `cell` with device `device` .

Ensures the wrapped `cell` is called with `tf.device(device)` .

Args:

- `cell` : An instance of `RNNCell` .
- `device` : A device string or function, for passing to `tf.device` .

`__call__`

```
__call__(
    inputs,
    state,
    scope=None
)
```

Run the cell on specified device.

`__deepcopy__`

```
__deepcopy__(memo)
```

`add_loss`

```
add_loss(
    losses,
    inputs=None
)
```

Add loss tensor(s), potentially dependent on layer inputs.

Some losses (for instance, activity regularization losses) may be dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs `a` and `b`, some entries in `layer.losses` may be dependent on `a` and some on `b`. This method automatically keeps track of dependencies.

The `get_losses_for` method allows to retrieve the losses relevant to a specific set of inputs.

Arguments:

- `losses` : Loss tensor, or list/tuple of tensors.
- `inputs` : Optional input tensor(s) that the loss(es) depend on. Must match the `inputs` argument passed to the `__call__` method at the time the losses are created. If `None` is passed, the losses are assumed to be unconditional, and will apply across all dataflows of the layer (e.g. weight regularization losses).

Raises:

- `RuntimeError` : If called in Eager mode.

`add_update`

```
add_update(
    updates,
    inputs=None
)
```

Add update op(s), potentially dependent on layer inputs.

Weight updates (for instance, the updates of the moving mean and variance in a BatchNormalization layer) may be

dependent on the inputs passed when calling a layer. Hence, when reusing a same layer on different inputs **a** and **b**, some entries in **layer.updates** may be dependent on **a** and some on **b**. This method automatically keeps track of dependencies.

The **get_updates_for** method allows to retrieve the updates relevant to a specific set of inputs.

This call is ignored in Eager mode.

Arguments:

- **updates** : Update op, or list/tuple of update ops.
- **inputs** : Optional input tensor(s) that the update(s) depend on. Must match the **inputs** argument passed to the **__call__** method at the time the updates are created. If **None** is passed, the updates are assumed to be unconditional, and will apply across all dataflows of the layer.

add_variable

```
add_variable(  
    name,  
    shape,  
    dtype=None,  
    initializer=None,  
    regularizer=None,  
    trainable=True,  
    constraint=None  
)
```

Adds a new variable to the layer, or gets an existing one; returns it.

Arguments:

- **name** : variable name.
- **shape** : variable shape.
- **dtype** : The type of the variable. Defaults to **self.dtype** or **float32**.
- **initializer** : initializer instance (callable).
- **regularizer** : regularizer instance (callable).
- **trainable** : whether the variable should be part of the layer's "trainable_variables" (e.g. variables, biases) or "non_trainable_variables" (e.g. BatchNorm mean, stddev).
- **constraint** : constraint instance (callable).

Returns:

The created variable.

Raises:

- **RuntimeError** : If called in Eager mode with regularizers.

apply

```
apply(  
    inputs,  
    *args,  
    **kwargs  
)
```

Apply the layer on a input.

This simply wraps `self.__call__`.

Arguments:

- `inputs`: Input tensor(s).
- `*args`: additional positional arguments to be passed to `self.call`.
- `**kwargs`: additional keyword arguments to be passed to `self.call`.

Returns:

Output tensor(s).

build

```
build(_)
```

call

```
call(  
    inputs,  
    **kwargs  
)
```

The logic of the layer lives here.

Arguments:

- `inputs`: input tensor(s).
- `**kwargs`: additional keyword arguments.

Returns:

Output tensor(s).

count_params

```
count_params()
```

Count the total number of scalars composing the weights.

Returns:

An integer count.

Raises:

- `ValueError` : if the layer isn't yet built (in which case its weights aren't yet defined).

get_input_at

```
get_input_at(node_index)
```

Retrieves the input tensor(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple inputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_input_shape_at

```
get_input_shape_at(node_index)
```

Retrieves the input shape(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple inputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_losses_for

```
get_losses_for(inputs)
```

Retrieves losses relevant to a specific set of inputs.

Arguments:

- `inputs` : Input tensor or list/tuple of input tensors. Must match the `inputs` argument passed to the `__call__` method at the time the losses were created. If you pass `inputs=None`, unconditional losses are returned, such as weight regularization losses.

Returns:

List of loss tensors of the layer that depend on `inputs`.

Raises:

- `RuntimeError` : If called in Eager mode.

get_output_at

```
get_output_at(node_index)
```

Retrieves the output tensor(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A tensor (or list of tensors if the layer has multiple outputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_output_shape_at

```
get_output_shape_at(node_index)
```

Retrieves the output shape(s) of a layer at a given node.

Arguments:

- `node_index` : Integer, index of the node from which to retrieve the attribute. E.g. `node_index=0` will correspond to the first time the layer was called.

Returns:

A shape tuple (or list of shape tuples if the layer has multiple outputs).

Raises:

- `RuntimeError` : If called in Eager mode.

get_updates_for

```
get_updates_for(inputs)
```

Retrieves updates relevant to a specific set of inputs.

Arguments:

- `inputs`: Input tensor or list/tuple of input tensors. Must match the `inputs` argument passed to the `__call__` method at the time the updates were created. If you pass `inputs=None`, unconditional updates are returned.

Returns:

List of update ops of the layer that depend on `inputs`.

Raises:

- `RuntimeError`: If called in Eager mode.

zero_state

```
zero_state(  
    batch_size,  
    dtype  
)
```

Except as otherwise noted, the content of this page is licensed under the [Creative Commons Attribution 3.0 License](#), and code samples are licensed under the [Apache 2.0 License](#). For details, see our [Site Policies](#). Java is a registered trademark of Oracle and/or its affiliates.

Last updated November 2, 2017.

Stay Connected

[Blog](#)

[GitHub](#)

[Twitter](#)

Support

[Issue Tracker](#)

[Release Notes](#)

[Stack Overflow](#)

English

[Terms](#) | [Privacy](#)