



WEEK 3 (1BM21CS213)

Outcomes:

Before configuring the IP address of the routers and end devices:




After configuring the IP address of the routers and end devices:



Configuration of routers:

Router0:

A screenshot of a software window titled "Router0" with tabs for "Physical", "Config", and "CLI". The "CLI" tab is active, showing the "IOS Command Line Interface". The interface displays a "System Configuration Dialog" with a prompt to continue with configuration (answered "no"). It then shows the execution of "enable" and "configure terminal". Two interfaces are configured: "FastEthernet 0/0" with IP address 10.0.0.1 and "Serial2/0" with IP address 20.0.0.1. Both interfaces are set to "no shutdown". Status messages indicate that both interfaces are now up. The window includes "Copy" and "Paste" buttons at the bottom right.

```
Router0
Physical Config CLI
IOS Command Line Interface

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!


Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fastEthernet 0/0
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#ip address 20.0.0.1 255.0.0.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Router(config-if)#exit
Router(config)#
```

Router1:

A screenshot of a software window titled "Router1" with tabs for "Physical", "Config", and "CLI". The "CLI" tab is active, showing the "IOS Command Line Interface". The interface displays a "System Configuration Dialog" with a prompt to continue with configuration (answered "no"). It then shows the execution of "enable" and "configure terminal". Two interfaces are configured: "Serial2/0" with IP address 20.0.0.2 and "Serial3/0" with IP address 30.0.0.1. Both interfaces are set to "no shutdown". Status messages indicate that both interfaces are now up. The window includes "Copy" and "Paste" buttons at the bottom right.

```
Router1
Physical Config CLI
IOS Command Line Interface

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!


Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial2/0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up

Router(config-if)#exiy
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to upt
Router(config)#interface Serial3/0
Router(config-if)#ip address 30.0.0.1 255.0.0.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Router(config-if)#exit
Router(config)#
```

Router2:



The screenshot shows a window titled "Router2" with three tabs: "Physical", "Config", and "CLI". The "CLI" tab is active, displaying the "IOS Command Line Interface". The interface shows a system configuration dialog that has been skipped. The user has entered the following commands and received the following responses:

```
Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface Serial3/0
Router(config-if)#ip address 30.0.0.2 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up

Router(config-if)#exit
Router(config)#exit
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to
Router(config)#interface fastEthernet 0/0
Router(config-if)#ip address 40.0.0.1 255.0.0.0
Router(config-if)#no shutdown


Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%IP-4-DUPADDR: Duplicate address 40.0.0.1 on FastEthernet0/0, sourced by 0060.5C0B.3D3A

Router(config-if)#exit
Router(config)#
```

At the bottom right of the CLI window, there are two buttons: "Copy" and "Paste".

In order to get reply from all the pings, we have to establish the IP Route, which can be done as follows:

Router0:



The screenshot shows the Router0 CLI interface with the following content:

```
Router0
Physical Config CLI
IOS Command Line Interface

Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
        i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
        * - candidate default, U - per-user static route, o - ODR
        P - periodic downloaded static route

Gateway of last resort is not set

C    10.0.0.0/8 is directly connected, FastEthernet0/0
C    20.0.0.0/8 is directly connected, Serial2/0
Router>enable
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#ip route 30.0.0.0 255.0.0.0 20.0.0.2
Router(config)#ip route 40.0.0.0 255.0.0.0 20.0.0.2
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console


Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
        i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
        * - candidate default, U - per-user static route, o - ODR
        P - periodic downloaded static route

Gateway of last resort is not set

C    10.0.0.0/8 is directly connected, FastEthernet0/0
C    20.0.0.0/8 is directly connected, Serial2/0
S    30.0.0.0/8 [1/0] via 20.0.0.2
S    40.0.0.0/8 [1/0] via 20.0.0.2
Router#
```

Copy Paste

Router1:

 Router1

Physical Config CLI

IOS Command Line Interface

```
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
        i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
        * - candidate default, U - per-user static route, o - ODR
        P - periodic downloaded static route

Gateway of last resort is not set

C    20.0.0.0/8 is directly connected, Serial2/0
C    30.0.0.0/8 is directly connected, Serial3/0
Router>enable
Router#configure terminal
Router#
% Invalid input detected at '^' marker.

Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#ip route 10.0.0.0 255.0.0.0 20.0.0.1
Router(config)#ip route 40.0.0.0 255.0.0.0 30.0.0.2
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
        i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
        * - candidate default, U - per-user static route, o - ODR
        P - periodic downloaded static route

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 20.0.0.1
C    20.0.0.0/8 is directly connected, Serial2/0
C    30.0.0.0/8 is directly connected, Serial3/0
S    40.0.0.0/8 [1/0] via 30.0.0.2
Router#
```

Copy Paste

Router2:

Router2

Physical Config CLI

IOS Command Line Interface

```
Router>show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    30.0.0.0/8 is directly connected, Serial3/0
C    40.0.0.0/8 is directly connected, FastEthernet0/0
Router>enable
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#ip route 10.0.0.0 255.0.0.0 30.0.0.1
Router(config)#ip route 20.0.0.0 255.0.0.0 30.0.0.1
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 30.0.0.1
S    20.0.0.0/8 [1/0] via 30.0.0.1
C    30.0.0.0/8 is directly connected, Serial3/0
C    40.0.0.0/8 is directly connected, FastEthernet0/0
Router#
```

Copy Paste

After establishing the IP Route, we get reply from all the pings:

