

To Restart the CORTEX CC services for using VTS simulator:

- 1- Open a new session on Putty or MobaXterm application with the following data

IP: 10.242.23.141

Port: 22

Login as: cortex

Password: cortex

```
      • MobaXterm 9.0 •
      (SSH client, X-server and networking tools)

> SSH session to cortex@10.242.23.141
  • SSH compression : ✓
  • SSH-browser      : ✓
  • X11-forwarding   : ✓ (remote display is forwarded through SSH)
  • DISPLAY          : ✓ (automatically set on remote server)

> For more info, ctrl+click on help or visit our website

Last unsuccessful login: Sun Sep 12 10:42:52 +03 2021 on ssh from 10.250.128.89
Last login: Sun Oct 10 10:44:48 +03 2021 on ssh from 10.250.128.89
*****
*
* Welcome to AIX Version 7.1!
*
* Please see the README file in /usr/lpp/bos for information pertinent to
* this release of the AIX Operating System.
*
*****
[YOU HAVE NEW MAIL]
*****
*
*                               BAJ Cortex (Credit)
*
* Environment : UAT(1)
*
*****
[dfistcrtxcap01-CREDIT-UAT-1]/cortex>#
```

Then enter **cs** then **y**

```
[dfistcrtxcap01-CREDIT-UAT-1]/cortex>#cs

ctxadmin - Copyright (c) 1987 AT&T; 1991 USL
          Copyright (c) 1994 Nomad Software Ltd.
          Copyright (c) 2010 Fidelity National Information Services, Inc.
                  and its subsidiaries. All rights reserved.

Shutdown all client processes? (y/n): y
```

Then **cb** then **y**

```
[dfistcrtxcap01-CREDIT-UAT-1]/cortex>#cs
ctxadmin - Copyright (c) 1987 AT&T; 1991 USL
           Copyright (c) 1994 Nomad Software Ltd.
           Copyright (c) 2010 Fidelity National Information Services, Inc.
           and its subsidiaries. All rights reserved.

Shutdown all client processes? (y/n): y
Shutting down all clients
Client COMMONITOR/FDS1: terminated
Client COMMONITOR/FDS2: terminated
Client FSDSRV/1: terminated
Client FSDSRV/2: terminated
Client FDSCLT/1: terminated
Client FDSCLT/2: terminated
Client FDSNMG/-: terminated
Client ISTROUTER/-: terminated
Client ISTCLT/-: terminated
Client TUXGATE/-: terminated
Client COMMONITOR/VISA: terminated
Client GENNMG/VISA: terminated
Client VISADRV/-: terminated
Client VISACLT/1: terminated
Client COMMONITOR/VISAS: terminated
Client GENNMG/VISAS: terminated
Client VISACLT/1: terminated
Client COMMONITOR/BNET1: terminated
Client GENNMG/BNET1: terminated
Client BNETDRV/1: terminated
Client BNETROUTER/1: terminated
Client BNETCLT1/1: terminated
Client COMMONITOR/BNETS: terminated
Client BNETDRV/SIM: terminated
Client BNETROUTER/SIM: terminated
Client BNETCLTS/1: terminated
Client CTXFORWARD/VISA: terminated
Client CTXFORWARD/BNET: terminated
Client CTXFORWARD/NOTIFQ: terminated
Client CTXFORWARD/NOTIFQ2: terminated
Client CTXFORWARD/NOTIFQ3: terminated
Client CTXFORWARD/ISTC: terminated
Client CTXFORWARD/FDSRSPQ: terminated
Client FDSUPLOAD/-: terminated
Client ISTDRV/-: terminated
Client VISAPVV/-: terminated
Client VISADRV/SIM: terminated
Client VISAROUTERS/-: terminated
Client CCSITEMCATCLT/-: terminated
[dfistcrtxcap01-CREDIT-UAT-1]/cortex>#cb

ctxadmin - Copyright (c) 1987 AT&T; 1991 USL
           Copyright (c) 1994 Nomad Software Ltd.
           Copyright (c) 2010 Fidelity National Information Services, Inc.
           and its subsidiaries. All rights reserved.

Boot all client processes? (y/n): y
```

Then **ca pcp** to check the status of the services:

```
[dfistcrtxcap01-CREDIT-UAT-1]/cortex>#ca pcp

ctxadmin - Copyright (c) 1987 AT&T; 1991 USL
          Copyright (c) 1994 Nomad Software Ltd.
          Copyright (c) 2010 Fidelity National Information Services, Inc.
          and its subsidiaries. All rights reserved.

Listing status of all clients
Client CTXFORWARD/VISA [19660912]: Running (last start Sun Oct 10 11:12:35 2021)
Client CTXFORWARD/BNET [18808930]: Running (last start Sun Oct 10 11:12:35 2021)
Client CTXFORWARD/NOTIFQ [21627060]: Running (last start Sun Oct 10 11:12:35 2021)
Client CTXFORWARD/NOTIFQ2 [22544406]: Running (last start Sun Oct 10 11:12:35 2021)
Client CTXFORWARD/NOTIFQ3 [14024842]: Running (last start Sun Oct 10 11:12:35 2021)
Client CTXFORWARD/ISTC [18546756]: Running (last start Sun Oct 10 11:12:35 2021)
Client CTXFORWARD/FDSRSPQ [20119660]: Running (last start Sun Oct 10 11:12:35 2021)
Client COMMONITOR/FDS1 [19857510]: Running (last start Sun Oct 10 11:12:35 2021)
Client COMMONITOR/FDS2 [21102746]: Running (last start Sun Oct 10 11:12:36 2021)
Client FDSDRV/1 [0]: Dead (exited 255)
Client FDSDRV/2 [0]: Dead (exited 255)
Client FDSCLT/1 [19464280]: Running (last start Sun Oct 10 11:12:36 2021)
Client FDSCLT/2 [20643964]: Running (last start Sun Oct 10 11:12:36 2021)
Client FDSNMG/- [20906116]: Running (last start Sun Oct 10 11:12:36 2021)
Client FDSUPLOAD/- [26018022]: Running (last start Sun Oct 10 11:12:36 2021)
Client ISTDV/- [0]: Dead (exited 1)
Client ISTRouter/- [0]: Dead (exited 1)
Client ISTCLT/- [21364882]: Running (last start Sun Oct 10 11:12:36 2021)
Client TUXGATE/- [19071052]: Running (last start Sun Oct 10 11:12:36 2021)
Client COMMONITOR/VISA [20316280]: Running (last start Sun Oct 10 11:12:36 2021)
Client GENNMG/VISA [20709514]: Running (last start Sun Oct 10 11:12:36 2021)
Client VISADRV/- [0]: Dead (exited 255)
Client VISARouter/- [20840598]: Running (last start Sun Oct 10 11:12:23 2021)
Client VISACLT/1 [19267666]: Running (last start Sun Oct 10 11:12:36 2021)
Client VISAPVV/- [18743396]: Running (last start Sun Oct 10 11:12:36 2021)
Client COMMONITOR/VISAS [20185216]: Running (last start Sun Oct 10 11:12:36 2021)
Client GENNMG/VISAS [19005522]: Running (last start Sun Oct 10 11:12:36 2021)
Client VISADRV/SIM [0]: Dead (exited 1)
Client VISAROUTERS/- [0]: Dead (exited 1)
Client VISACLT/1 [21168268]: Running (last start Sun Oct 10 11:12:36 2021)
Client COMMONITOR/BNET1 [21299344]: Running (last start Sun Oct 10 11:12:36 2021)
Client GENNMG/BNET1 [21233828]: Running (last start Sun Oct 10 11:12:36 2021)
Client BNETDRV/1 [0]: Dead (exited 255)
Client BNETROUTER/1 [21495960]: Running (last start Sun Oct 10 11:12:36 2021)
Client BNETCLT/1 [21954728]: Running (last start Sun Oct 10 11:12:36 2021)
Client COMMONITOR/BNETS [20775050]: Running (last start Sun Oct 10 11:12:36 2021)
Client BNETDRV/SIM [0]: Dead (exited 255)
Client BNETROUTER/SIM [18677840]: Running (last start Sun Oct 10 11:12:36 2021)
Client BNETCLTS/1 [19791972]: Running (last start Sun Oct 10 11:12:36 2021)
Client CCSITEMCATCLT/- [20447354]: Running (last start Sun Oct 10 11:12:36 2021)
[dfistcrtxcap01-CREDIT-UAT-1]/cortex>#
```