

Assignment on Routing Information Protocol

Name: YOUSUF MIA

ID No: 191-15-2360

SEC: PC-A

Router 0:

Router>enable

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface Serial2/0

Router(config-if)#ip address 10.0.0.2 255.0.0.0

Router(config-if)#ip address 10.0.0.2 255.0.0.0

Router(config-if)#clock rate 56000

This command applies only to DCE interfaces

Router(config-if)#clock rate 64000

This command applies only to DCE interfaces

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

ip address 20.0.0.1 255.0.0.0

Router(config-if)#ip address 20.0.0.1 255.0.0.0

Router(config-if)#clock rate 64000

Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial2/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

Router con0 is now available

Press RETURN to get started.

```
Router>en
Router#config T
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 10.0.0.0
Router(config-router)#network 20.0.0.0
Router(config-router)#exit
Router(config)#
```

Router 1:

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 100.0.0.1 255.0.0.0
Router(config-if)#ip address 100.0.0.1 255.0.0.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
```

```
Router(config-if)#ip address
% Incomplete command.
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#clock rate 64000
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#ip address 40.0.0.2 255.0.0.0
Router(config-if)#ip address 40.0.0.2 255.0.0.0
Router(config-if)#clock rate 64000
Router(config-if)#no shutdown
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
```

Router con0 is now available

Press RETURN to get started.

```
Router>en
Router#config T
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#routing rip
^
% Invalid input detected at '^' marker.
Router(config)#router rip
Router(config-router)#network 100.0.0.0
Router(config-router)#network 10.0.0.0
Router(config-router)#network 40.0.0.0
Router(config-router)#exit
Router(config)#
```

Router 2:

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 200.0.0.1 255.255.255.0
Router(config-if)#ip address 200.0.0.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

```
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
clock rate 64000

This command applies only to DCE interfaces

```
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial2/0
Router(config-if)#ip address 30.0.0.1 255.0.0.0
Router(config-if)#shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to administratively down
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to down
no shutdown

```
Router(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up
```

```
Router(config-if)#exit
Router(config)#interface Serial3/0
Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
ip address 20.0.0.2 255.0.0.0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#clock rate 64000
This command applies only to DCE interfaces
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
```

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

Router con0 is now available

Press RETURN to get started.

```
Router>en
Router#config T
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 20.0.0.0
Router(config-router)#network 200.0.0.0
Router(config-router)#network 30.0.0.0
Router(config-router)#exit
Router(config)#
```

Router 3:

Router>enable

Router#

Router#configure terminal

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#interface Serial2/0

Router(config-if)#ip address 40.0.0.1 255.0.0.0

Router(config-if)#ip address 40.0.0.1 255.0.0.0

Router(config-if)#clock rate 64000

This command applies only to DCE interfaces

Router(config-if)#no shutdown

Router(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Router(config-if)#exit

Router(config)#interface Serial3/0

Router(config-if)#no shutdown

Router(config-if)#ip address 30.0.0.2 255.0.0.0

Router(config-if)#ip address 30.0.0.2 255.0.0.0

Router(config-if)#clock rate 64000

Router(config-if)#

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

%LINK-3-UPDOWN: Interface Serial3/0, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to down

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up

Router con0 is now available

Press RETURN to get started.

```
Router>en
Router#config T
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 30.0.0.0
Router(config-router)#network 40.0.0.0
Router(config-router)#exit
Router(config)#
```

