

ZEST Coin Multi Masternode Guide

Controller-Cold-Setup


This is the advised Method to setup your Masternodes. The wallet containing the coins does not have to be exposed and can run on your local computer. It does not have to run all the time and you are not vulnerable to someone hacking your VPS because all he can do when he hacked your VPS is stop your MNs but not steal your coins!

Desktop Wallet Setup


In the first steps the desktop wallet will be setup. This is the wallet you can run on your local PC. When the masternodes are connected this wallet can be closed and the PC does not have to run in order for the masternodes to generate rewards.

We will create an address, private key and transaction for each masternode (MN in the following) and show the necessary steps for configuration.

1. Open Console: Tools → Debug Console




2. Type “getaccountaddress MN1” and press Enter.



Repeat this step for the amount of masternodes you want to setup as shown. Make sure you count up (MN1, MN2 etc.)

ZEST Coin Multi Masternode Guide

 Receiving addresses ? ×

These are your ZST addresses for receiving payments. It is recommended to use a new receiving address for each transaction.

Label	Address
MN1	ZZdytiFBCPkoWfh8jruA4eDPGPBwLYFc5G
MN2	ZTHtAXFijnrriuwigozlXAMwgr7FKD86hY
Standard	ZDkblpnSghCSXYgPkBX1o7y5N157f5TRj

+ New Copy Export Close

These are the addresses that will be associated with the MNs. You can view all you created addresses under File → Receiving Addresses

3. Send exactly 2500 coins to each MN address

Pay To:

ZZdytiFBCPkoWfh8jruA4eDPGPBwLYFc5G

Label:

MN1

Amount:

2 500.00000000

↑

↓

ZST

Pay To:

ZTHtAXFijnrriuwigozlXAMwgr7FKD86hY

Transaction Fee:

0.00010000 ZST/kB

Choose...

Send


Clear All

+ Add Recipient

Klick on “add recipient” to add lines so you can send to all nodes in one transaction.

ZEST Coin Multi Masternode Guide

4. Setup MNs in config: Tools → Open Masternode Configuration File




Your text editor will open with the configuration file.

alias IP:port masternodeprivkey txhash outputindex

We will now add a Line for each MN with the following Format:

- a. Begin by entering and alias IP:port
 - i. Alias: the name of the MN receiving address (we named them MN1, MN2, ...)
 - ii. IP: The static IP of your linux server – if you don't have one right now go to the next section "Getting a VPS" before you continue.
 - iii. port: A port the MN will connect to. The port is not fixed and multiple nodes can run on one server but need different ports.




You can have more than one node per IP just adjust the ports. We start with 8001 but you can choose any free port!

- b. Next we get the "masternodeprivkey"
 - i. Open debug console again, type "masternode genkey" and press enter

```
00:47:44  ← masternode genkey
00:47:44  → 2a1Z6b1BhTEzztFYrYhUcenAReP6MJSYbN3RahmuUbJpx3Umtol
00:47:45  ← masternode genkey
00:47:45  → 2ZZCfcYSwoFpLEctjm7HvvEJJ1wvVf13vuxdytwHT5j1bfbxfwB
```

- ii. Repeat the line for each MN you want to setup
 - iii. Copy the output keys to the config



The private keys are used for voting and identify you as the real owner so don't share them.

- c. Next we will add txhash and outputindex
 - i. Go to the debug console again, type "masternode outputs" and press enter

ZEST Coin Multi Masternode Guide

- ii. If you send the coins in one transaction the “txhash” will be the same. If

```
00:50:23 ➡ masternode outputs
00:50:23 ➡ [
  {
    "txhash": "52b27d326649cf6e917ff141f3a9ed03421dd076797a9ee71f4d9ac9a7ff0d37",
    "outputidx": 0
  },
  {
    "txhash": "52b27d326649cf6e917ff141f3a9ed03421dd076797a9ee71f4d9ac9a7ff0d37",
    "outputidx": 1
  }
]
```


you add a masternode later, another tuple will be added. So every masternode has a unique pair of txhash and outputindex

- iii. Copy the information to the config file (Make sure you don't forget the index!)

```
masternode.conf - Editor
Datei Bearbeiten Format Ansicht ?
MN1 217.163.23.69:8001 2a1Z6b1BhTEzztFYrYhUcenAReP6M3SYbN3RahmuUb3px3Umtol 52b27d326649cf6e917ff141f3a9ed03421dd076797a9ee71f4d9ac9a7ff0d37 0
MN2 217.163.23.69:8002 2Z2CfcYSwofpLEctjm7HvvEJJ1wvVf13vuxdytwHT5j1bfbxwB 52b27d326649cf6e917ff141f3a9ed03421dd076797a9ee71f4d9ac9a7ff0d37 1
```

This is what your config should finally look like.

5. Save the file and restart the wallet.



Alias	Address	Protocol	Status	Active	Last Seen (UTC)	Pubkey
MN1	217.163.23.69:8001	-1	MISSING	00m:00s	1970-01-01 00:00	
MN2	217.163.23.69:8002	-1	MISSING	00m:00s	1970-01-01 00:00	

Verify now that your MN are shown in the Masternodes tab.


Getting a VPS

For the cold wallets you first need a linux VPS. You can get very cheap ones for 5\$ here: <https://www.vultr.com/?ref=7285424>. These can run around 5 ZEST masternode instances though it might be a good idea to split your MNs across some different Servers. The more isolation you have the less likely you are hit big by a server outage☺.

After registration you get to the Dashboard. You have to do the first payment with something else then Bitcoin. After the first payment you can pay the servers in BTC.

ZEST Coin Multi Masternode Guide

6. Deploy the server





Hit the plus top right to add new instances


7. Choose a region near you. It does not really matter.


2 Server Type


64 bit OS 32 bit OS Application Upload ISO ISO Library Backup Snapshot


**CentOS**
SELECT VERSION


**CoreOS**
Stable x64

**Debian**
SELECT VERSION


**Fedora**
SELECT VERSION

**FreeBSD**
SELECT VERSION

**OpenBSD**
6 x64

**Ubuntu**
SELECT VERSION

17.10 x64
16.04 x64
14.04 x64

**Windows**
SELECT VERSION

3 Server Size

Temporarily Sold Out

20 GB SSD

\$2.50/mo
\$0.004/h

1 CPU
512MB Memory
500GB Bandwidth

25 GB SSD

\$5/mo
\$0.007/h

1 CPU
1024MB Memory
1000GB Bandwidth

40 GB SSD

\$10/mo
\$0.015/h

1 CPU
2048MB Memory
2000GB Bandwidth

Servers Qty: Summary: **\$5.00/mo** (\$0.007/hr) [Deploy Now](#)

- As "Server Type" choose Ubuntu and klick 16.04 (Important don't take 17.10!)
- As Server Size choose the 5\$ instance with 1GB Ram. If available you can choose the 2.50\$ one if you only want to run one or two nodes on it.

ZEST Coin Multi Masternode Guide

- c. Scroll down and give the node a name.
- d. After that click “Deploy now” in the overview you should see this:



8. Connect to the Server.

- e. You will need some SSH tool connect. I use “Royal-TS” to manage several connections at once. It’s a bit harder getting used to but has real value.
- f. To connect with “putty” a basic tool refer to [this guide](#)
- g. You can find username (root) and password when you click on the newly created instance. The installation has to finish before!
- h. Note: pasting your clipboard is “right click”

Automatic server installation and setup.

9. Download and execute script on VPS:

```
wget https://raw.githubusercontent.com/XeZzoR/scripts/master/ZEST/setup.sh
chmod 755 setup.sh
./setup.sh
```

This process is interactive and takes several minutes.

```
root@ZEST:~# ./setup.sh
*****
* Ubuntu 16.04 is the recommended operating system for this install. *
*
* This script will install and configure your ZEST Coin masternodes. *
*****

!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
!
! Make sure you double check before hitting enter !
!
!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!

Do you want to install all needed dependencies (no if you did it before)? [y/n]
y
```

Enter y and press enter when you first setup the server. All dependencies and needed programs will be installed (takes some minutes)

```
How many nodes do you want to create on this server?, followed by [ENTER]:
2
```

Enter the number of masternodes you want to run on the server (2 in my case)

ZEST Coin Multi Masternode Guide

```
Enter alias for new node
mn1

Enter port for node mn1 (Any valid free port matching config from steps before: i.E. 8001)
8001

Enter RPC Port (Any valid free port: i.E. 9001)
9001

Enter masternode private key for node mn1
2a1Z6b1BhTEzztFYrYhUcenAReP6MJSYbN3RahmuUbJpx3Umtol
Skipping adding existing rule
Skipping adding existing rule (v6)
Zest server starting
```

Enter the asked information. The alias is to give each node a unique name and control it. Enter port and masternode key which you configured before in the desktop wallet. Also unique free rpc port is needed (We start with 9001 and count up here). The input process repeats for every node you want to configure (2 times in my case)

The name you enter is always converted to lowercase! Only use alphanumeric characters!

If you made an error when typing the interactive stuff: ctrl+c and restart the script 😊

10. Controlling the masternode

- The script from the last step already started all wallets on VPS
- Type “source .bashrc” in console
- Each MN has now its own control script under ~/bin (named with alias you typed before)
- To see if everything works type “zestcoin-cli_mn1.sh mnsync status”

```
root@ZEST:~# zest-cli_mn1.sh mnsync status
{
  "IsBlockchainSynced": true,
  "lastMasternodeList": 0,
  "lastMasternodeWinner": 0,
  "lastBudgetItem": 0,
  "lastFailure": 0,
  "nCountFailures": 0,
  "sumMasternodeList": 0,
  "sumMasternodeWinner": 0,
  "sumBudgetItemProp": 0,
  "sumBudgetItemFin": 0,
  "countMasternodeList": 4,
  "countMasternodeWinner": 4,
  "countBudgetItemProp": 1,
  "countBudgetItemFin": 1,
  "RequestedMasternodeAssets": 4,
  "RequestedMasternodeAttempt": 1
}
```

Every node has a script “zestcoin-cli_ ALIAS.sh”, “zestcoind_ ALIAS.sh”. Always use these scripts and not the daemon directly.


ZEST Coin Multi Masternode Guide

```
root@ZEST:~# zest-cli_mn1.sh getinfo
{
  "version": 1000061,
  "protocolversion": 70913,
  "walletversion": 61000,
  "balance": 0.00000000,
  "blocks": 2101,
  "timeoffset": 0,
  "connections": 12,
  "proxy": "",
  "difficulty": 2104.655860069281,
  "testnet": false,
  "moneysupply": 1502099.99351910,
  "keypoololdest": 1526795045,
  "keypoolsize": 1001,
  "paytxfee": 0.00000000,
  "relayfee": 0.00010000,
  "staking status": "Staking Not Active",
  "errors": ""
}
```

“zestcoin-cli_mn1.sh” will show you amount of blocks and connection count!

- e. If sync is finished go to your desktop wallet and start MNs in the masternode tab (unlock wallet before).

Alias	Address	Protocol	Status	Active	Last Seen (UTC)	Pubkey
MN1	217.163.23.69:8001	70912	ENABLED	00m:00s	2018-04-30 22:54	ZZdytiFBCPkoWfh8jruA4eDPGPBwL...
MN2	217.163.23.69:8002	70912	ENABLED	00m:00s	2018-04-30 22:54	ZTHtAXFijnriuwioqz1XAMwgr7FKD...



- f. Now check if MNs are running on the VPS with
“zestcoin-cli_mn1.sh masternode status”

```
root@ZEST:~# zest-cli_mn1.sh masternode status
{
  "txhash": "a3a8b1f9e44decd03577085aa2f7f371e9c4c64a7fc42a08ab33388f2be05bbc"
  "outputidx": 0,
  "netaddr": "217.163.23.69:8001",
  "addr": "ZYqoxp1XjL3DWxqMJDsjyPZTgRpaRwcE1P",
  "status": 4,
  "message": "Masternode successfully started"
}
```

This shows you that the MN is successfully started! Repeat this for all MNs to ensure they are running.

- g. You can close your Desktop wallet after a while if the time starts counting up.

Adding more nodes to existing VPS

To add more ZEST MNs to an existing server setup with the setup_multi.sh script before just restart the script and type “n” when asked if you want to install the dependencies at the beginning. After that just follow the steps from before in the interactive script.