



User Manual
(Implementation Guide)

UN/EDIFACT MESSAGE

COPRAR
(Container discharge/loading order)

Version 2.0

D00B



Version : 2.0
Date : March 2003
Source : SMDG User Group for Shipping Lines and Container Terminals

© SMDG

Information in this document is subject to change without notice.

The SMDG claims full copyright to this manual and its contents, however, the manual may be copied and used by anyone, without the consent of SMDG.

It is not allowed to change the contents of this manual!



CONTENTS

0.	Introduction	4
1.	General	4
2.	Status Indicators and Usage Indicators....	5
3.	Document Maintenance.....	6
4.	Segment Table	7
5.	Message Structure Diagram	9
6.	Message Description	12
7.	Sample Message	59



0. INTRODUCTION

This User Manual has been developed by the SMDG User Group for Shipping Lines and Container Terminals, a "Global User Group" under the auspices of UN/CEFACT.

This User Manual is based upon the UN/EDIFACT D.00B directory and the ITIGG document "Principles and Rules for the implementation of transport EDI messages – Transport Equipment Movements – Maritime-related container messages", version 1.3.1, dated September 1996.

This User Manual provides guidance as to the recommended usage of codes, qualifiers, data elements, composites, segments and groups of segments in the D.00B COPRAR message. The intention is to assist developers to ensure consistent use of the COPRAR message throughout the worldwide trade and transport community.

1. GENERAL

Formal Definition

"A message to order to the container terminal that the containers specified have to be discharged from a seagoing vessel or have to be loaded into a seagoing vessel. This message is part of a total set of container-related messages. These messages serve to facilitate the intermodal handling of containers by streamlining the information exchange. The business scenario for the container messages is clarified in a separate document, called "Guide to the scenario of EDIFACT container messages".

The COPRAR message is used to transmit an order to load containers on or discharge containers from a seagoing vessel. This message is commonly sent by the shipping line (or it's agent) to the terminal operator handling the vessel.

In addition to containers to be loaded or discharged, the COPRAR message may also be used to transmit details on containers that are to be shifted on board the vessel or containers that are to be discharged and reloaded (restowed) onto the vessel.



2. STATUS INDICATORS AND USAGE INDICATORS

Status Indicators

Status Indicators (“M” and “C”) form part of the UN/EDIFACT standard and indicate a minimum requirement to fulfil the needs of the message structure. They are not adequate for implementation purposes. The Status Indicators are :

<i>Value</i>	<i>Description</i>
M	Mandatory The entity marked as such must appear in all messages, and apply to these messages as well as to any associated implementation guidelines (and consequently is also a Usage Indicator).
C	Conditional The entity is used by agreement between trading partners.

Usage Indicators

Usage Indicators are implementation–related indicators that further detail the use of “Conditional” Status Indicators. Usage Indicators are applied at all levels of the guidelines and shown adjacent to data items such as segment groups, segments, composite data elements and simple data elements. They dictate the agreed usage of the data items or entities. The Usage Indicators are :

<i>Value</i>	<i>Description</i>
M	Mandatory Indicates the item is mandatory in the UN/EDIFACT message.
R	Required Indicates the item must be transmitted in this implementation.
D	Dependent Indicates that the use of the item is depending on a well-defined condition or set of conditions. These conditions must be clearly specified in the relevant implementation guideline.
O	Optional Indicates that this item is at the need or discretion of both trading partners.
X	Not Used Indicates that this item is not to be used in this implementation.

Where an item within a segment group, segment or composite data element is marked with Usage Indicators “M” or “R”, but the segment group, segment or composite data element has been marked “O” or “D” (or for that matter “X”), the item is only to be transmitted when the segment group, segment or composite of which it is a part, is used.



3. DOCUMENT MAINTENANCE

The data content of this document has been prepared and approved by SMDG and no alteration may be made to the content of this document without reference to and approval of SMDG.

Any remarks, questions, amendments or requested alterations to this document are to be addressed to :

SMDG Secretariat
Seattleweg 7
3195 ND Rotterdam – Pernis
The Netherlands

Phone: +31- (0)10 - 2941100
Fax: +31- (0)10 - 2941105
E-mail: secretariat@smdg.org
WWW www.smdg.org

Jacco Bruijnes
c/o Maersk Benelux B.V.
P.O. Box 999
3160 AD Rhoon
The Netherlands

Phone: +31 – (0)10 5030771
Facsimile: +31 – (0)10 5030749
E-mail benedi@maersk.com



COPRAR Container Discharge/Loading Order Message

Introduction:


A message to order to the container terminal that the containers specified have to be discharged from a seagoing vessel or have to be loaded into a seagoing vessel.


This message is part of a total set of container-related messages. These messages serve to facilitate the intermodal handling of containers by streamlining the information exchange. The business scenario for the container messages is clarified in a separate document, called: 'Guide to the scenario of EDIFACT container messages'.


	Pos. No.	Seg. ID	Name	Req. Des.	Max.Use	Group Repeat	Notes and Comments
M	0010	UNH	Message Header	M	1		
M	0020	BGM	Beginning of Message	M	1		
R	0030	DTM	Date/Time/Period	C	9		
O	0050		Segment Group 1: RFF	C		9	
M	0060	RFF	Reference	M	1		
M	0080		Segment Group 2: TDT-RFF-SG3	M		1	
M	0090	TDT	Details of Transport	M	1		
O	0110	RFF	Reference	C	9		
O	0120		Segment Group 3: LOC-DTM	C		9	
M	0130	LOC	Place/Location Identification	M	1		
O	0140	DTM	Date/Time/Period	C	9		
M	0160		Segment Group 4: NAD-SG5	M		9	
M	0170	NAD	Name and Address	M	1		
O	0180		Segment Group 5: CTA-COM	C		9	
M	0190	CTA	Contact Information	M	1		
O	0200	COM	Communication Contact	C	9		
M	0210		Segment Group 6: EQD-RFF-EQN-TMD-DTM-LOC-MEA-DIM-SG7-SEL-FTX-SG8-EQA-HAN-SG10-NAD	M		9999	
M	0220	EQD	Equipment Details	M	1		
O	0230	RFF	Reference	C	9		
O	0240	EQN	Number of Units	C	1		
O	0250	TMD	Transport Movement Details	C	9		
O	0260	DTM	Date/Time/Period	C	9		
R	0270	LOC	Place/Location Identification	C	9		
O	0280	MEA	Measurements	C	9		
O	0290	DIM	Dimensions	C	9		
O	0300		Segment Group 7: TMP-RNG	C		9	
M	0310	TMP	Temperature	M	1		
O	0320	RNG	Range Details	C	1		
O	0330	SEL	Seal Number	C	9		
O	0340	FTX	Free Text	C	9		
O	0360		Segment Group 8: DGS-FTX-SG9	C		99	
M	0370	DGS	Dangerous Goods	M	1		
O	0380	FTX	Free Text	C	9		
O	0400		Segment Group 9: CTA-COM	C		9	
M	0410	CTA	Contact Information	M	1		
O	0420	COM	Communication Contact	C	9		



O	0430	EQA	Attached Equipment	C	9
O	0440	HAN	Handling Instructions	C	9
O	0450		Segment Group 10: TDT-DTM-RFF-SG11	C	1
M	0460	TDT	Details of Transport	M	1
O	0470	DTM	Date/Time/Period	C	9
O	0480	RFF	Reference	C	9
O	0490		Segment Group 11: LOC	C	9
M	0500	LOC	Place/Location Identification	M	1
O	0520	NAD	Name and Address	C	9
O	0530	CNT	Control Total	C	1
M	0540	UNT	Message Trailer	M	1









Segment: **UNH** Message Header

Position: 0010

Group:

Level: 0

Usage: Mandatory

Max Use: 1

Purpose: A service segment starting and uniquely identifying a message. The message type code for the Container discharge/loading order message is COPRAR.
 Note: Container discharge/loading order messages conforming to this document must contain the following data in segment UNH, composite S009:
 Data element 0065 COPRAR 0052 D 0054 00B 0051 UN

Comments:

Notes: *Sample segment :*
UNH+100011544142+COPRAR:D:00B:UN:SMDG20'

Data Element Summary

	<u>Data</u>	<u>Component</u>		<u>Attributes</u>
	<u>Element</u>	<u>Element</u>	<u>Name</u>	
M	0062		MESSAGE REFERENCE NUMBER <i>Unique message reference assigned by the sender. This reference must also be transmitted in the UNT segment.</i>	M 1 an..14
M	S009		MESSAGE IDENTIFIER	M 1
M		0065	Message type identifier COPRAR Container discharge/loading order message	M an..6
M		0052	Message type version number D Draft version/UN/EDIFACT Directory	M an..3
M		0054	Message type release number 00B Release 2000 - B	M an..3
M		0051	Controlling agency UN UN/CEFACT	M an..2
R		0057	Association assigned code	C an..6
O	0068		SMDG20 SMDG Version 2.0 COMMON ACCESS REFERENCE <i>Additional message reference (if required)</i>	C 1 an..35
X	S010		STATUS OF THE TRANSFER	C 1
X		0070	Sequence message transfer number	M n..2
X		0073	First/last sequence message transfer indication	C a1



Segment: **BGM** Beginning of Message
Position: 0020
Group:
Level: 0
Usage: Mandatory
Max Use: 1
Purpose: A segment to indicate the beginning of a message and to transmit identifying number and the further specification of the message type (in data element 1001: Document name code), such as Loading order, Discharge order.

Comments:

Notes: *Sample segment :*
BGM+121+100011544142+9+AB'

Data Element Summary

	<u>Data</u>	<u>Component</u>		<u>Attributes</u>
	<u>Element</u>	<u>Element</u>	<u>Name</u>	
R	C002		DOCUMENT/MESSAGE NAME	C 1
R		1001	Document name code	C an..3
		118	Transport discharge instruction	
		121	Transport loading instruction	
X		1131	Code list identification code	C an..17
X		3055	Code list responsible agency code	C an..3
X		1000	Document name	C an..35
R	C106		DOCUMENT/MESSAGE IDENTIFICATION	C 1
R		1004	Document identifier	C an..35
			<i>Sender's unique reference number</i>	
X		1056	Version identifier	C an..9
X		1060	Revision identifier	C an..6
R	1225		MESSAGE FUNCTION CODE	C 1 an..3
			<i>If code 1 or 5 is used, reference number of the message which is being cancelled/replaced must appear in the header level RFF using the code ACW in e1153.</i>	
		1	Cancellation	
		5	Replace	
		9	Original	
O	4343		RESPONSE TYPE CODE	C 1 an..3
		AB	Message acknowledgement	



Segment: **DTM** Date/Time/Period
Position: 0030
Group:
Level: 1
Usage: Conditional (Required)
Max Use: 9
Purpose: A segment to indicate a date and/or time applying to the whole message, such as date and time of document or message issue.
Comments:
Notes: *Sample segment :*
DTM+137:200211150114:203'

Data Element Summary				
	Data	Component		Attributes
	<u>Element</u>	<u>Element</u>	<u>Name</u>	
M	C507		DATE/TIME/PERIOD	M 1
M		2005	Date or time or period function code qualifier 137 Document/message date/time	M an..3
R		2380	Date or time or period value Date/time that the message was prepared.	C an..35
R		2379	Date or time or period format code 203 CCYYMMDDHHMM	C an..3



Segment: **RFF** Reference
Position: 0060 (Trigger Segment)
Group: Segment Group 1 (Reference) Conditional (Optional)
Level: 1
Usage: Mandatory
Max Use: 1
Purpose: A segment to express a reference which applies to the entire message, such as: -
container discharge/loading order reference - reference to previous message
Comments:
Notes: *Sample segment :*
RFF+AAY:58S/0220'

Data Element Summary

	Data	Component		Attributes	
	<u>Element</u>	<u>Element</u>	<u>Name</u>		
M	C506	1153	REFERENCE	M	1
M			Reference code qualifier	M	an..3
			AAY		Carrier's agent reference number
			ACA		Cargo acceptance order reference number
			ACW		Reference number to previous message
			AKA		Container disposition order reference number
			ARJ		Personal identity card number
			ATX		Transport equipment acceptance order reference
			ATY		Transport equipment release order reference
			BM		Bill of lading number
			BN		Booking reference number
			CN		Carrier's reference number
			RE		Release number
R		1154	Reference identifier Reference number	C	an..70
X		1156	Document line identifier	C	an..6
X		4000	Reference version identifier	C	an..35
X		1060	Revision identifier	C	an..6



Segment: **TD** Details of Transport
Position: 0090 (Trigger Segment)
Group: Segment Group 2 (Details of Transport) Mandatory
Level: 1
Usage: Mandatory
Max Use: 1
Purpose: A segment identifying the voyage of the vessel relevant to the message (main transport).

Comments:

Notes: *Sample segment :*
TDT+20+0220+1++MAE:172:20:MAERSK+++8212661:146:11:SL PRIDE:US'

Data Element Summary

	Data	Component			
	<u>Element</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>	
M	8051		TRANSPORT STAGE CODE QUALIFIER	M 1 an..3	
			20 Main-carriage transport		
D	8028		MEANS OF TRANSPORT JOURNEY IDENTIFIER	C 1 an..17	
			Vessel operator's voyage number		
			<i>Either this element or the Group 2 RFF must be used to specify a voyage number.</i>		
R	C220		MODE OF TRANSPORT	C 1	
R		8067	Transport mode name code	C an..3	
			1 Maritime transport (ocean)		
X		8066	Transport mode name	C an..17	
O	C228		TRANSPORT MEANS	C 1	
O		8179	Transport means description code	C an..8	
			Means of transport code (UN/ECE Recommendation 28)		
O		8178	Transport means description	C an..17	
			Type of means of transport (free text)		
R	C040		CARRIER	C 1	
R		3127	Carrier identifier	C an..17	
			Vessel operator's code		
O		1131	Code list identification code	C an..17	
			172 Carriers		
O		3055	Code list responsible agency code	C an..3	
			20 BIC (Bureau International des Containeurs)		
			87 Assigned by carrier		
			166 US, National Motor Freight Classification Association		
			184 AU, ACOS (Australian Chamber of Shipping)		
			SMDG (Shipplanning Message Development Group)		
			Temporary code		
			ZZZ Mutually defined		
O		3128	Carrier name	C an..35	
			Vessel operator's name (free text)		
X	8101		TRANSIT DIRECTION INDICATOR CODE	C 1 an..3	
X	C401		EXCESS TRANSPORTATION INFORMATION	C 1	
X		8457	Excess transportation reason code	M an..3	
X		8459	Excess transportation responsibility code	M an..3	
X		7130	Customer shipment authorisation identifier	C an..17	
D	C222		TRANSPORT IDENTIFICATION	C 1	
D		8213	Transport means identification name identifier	C an..9	
			Lloyd's (IMO) number		

Either this element or the Group 2 RFF must be used to specify a vessel id.



O	1131	Code list identification code	C	an..17
		146 Means of transport identification		
O	3055	Code list responsible agency code	C	an..3
		11 Lloyd's register of shipping		
O	8212	Transport means identification name	C	an..35
		Vessel name (free text)		
O	8453	Transport means nationality code	C	an..3
		Flag of means of transport (ISO country code)		
X	8281	TRANSPORT MEANS OWNERSHIP INDICATOR CODE	C	1 an..3



Segment: **RFF** Reference
Position: 0110
Group: Segment Group 2 (Details of Transport) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to provide alternative (non vessel operator's) voyage number and other references related to the main carriage means of transport.
Comments:
Notes: *Sample segment :*
RFF+VM:WDA3673'

Data Element Summary

	<u>Data Element</u>	<u>Component Element</u>	<u>Name</u>	<u>Attributes</u>	
M	C506		REFERENCE	M	1
M		1153	Reference code qualifier	M	an..3
			ATZ Ship's stay reference number		
			MA Ship notice/manifest number		
			VM Vessel identification		
			VON Voyage number		
R		1154	Reference identifier	C	an..70
			Callsign (if C506.e1153 = 'VM')		
			Alternative (non vessel operator's) voyage number (if C506.e1153 = 'VON')		
			Manifest number (if C506.e1153 = 'MA')		
			Other reference (if C506.e1153 = 'ATZ')		
X		1156	Document line identifier	C	an..6
X		4000	Reference version identifier	C	an..35
X		1060	Revision identifier	C	an..6



Segment: **LOC** Place/Location Identification
Position: 0130 (Trigger Segment)
Group: Segment Group 3 (Place/Location Identification) Conditional (Optional)
Level: 2
Usage: Mandatory
Max Use: 1
Purpose: A segment to identify a location related to the means of transport, such as: - place of departure/arrival (terminal within the port)

Comments:

Notes: *Sample segment :*
LOC+9+NLRTM:139:6:ROTTERDAM+APMROT:72:SMD:APM
TERMINALS+8200:266:ZZZ'

Data Element Summary

	Data Element	Component Element	Name	Attributes
M	3227		LOCATION FUNCTION CODE QUALIFIER	M 1 an..3
			9 Place/port of loading	
			11 Place/port of discharge	
R	C517		LOCATION IDENTIFICATION	C 1
O		3225	Location name code	C an..25
			UNLOCODE	
O		1131	Code list identification code	C an..17
			139 Port	
O		3055	Code list responsible agency code	C an..3
			6 UNECE (United Nations - Economic Commission for Europe)	
O		3224	Location name	C an..256
			Port name (free text)	
O	C519		RELATED LOCATION ONE IDENTIFICATION	C 1
O		3223	First related location name code	C an..25
			1st related location code	
O		1131	Code list identification code	C an..17
			72 Container terminal	
			266 Marine berth	
			267 Marine wharf	
O		3055	Code list responsible agency code	C an..3
			9 EAN (International Article Numbering association)	
			184 AU, ACOS (Australian Chamber of Shipping)	
			SMD SMDG (Shipplanning Message Development Group)	
			Temporary code	
			ZZZ Mutually defined	
O		3222	First related location name	C an..70
			1st related location name (free text)	
O	C553		RELATED LOCATION TWO IDENTIFICATION	C 1
O		3233	Second related location name code	C an..25
			2nd related location code	
O		1131	Code list identification code	C an..17
			72 Container terminal	
			266 Marine berth	
			267 Marine wharf	
O		3055	Code list responsible agency code	C an..3
			9 EAN (International Article Numbering association)	
			184 AU, ACOS (Australian Chamber of Shipping)	
			SMD SMDG (Shipplanning Message Development Group)	
			Temporary code	



		ZZZ	Mutually defined		
O		3232	Second related location name	C	an..70
			2nd related location name (free text)		
X	5479		RELATION CODE	C	1 an..3



Segment: **DTM** Date/Time/Period
Position: 0140
Group: Segment Group 3 (Place/Location Identification) Conditional (Optional)
Level: 3
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to specify date(s) and time(s) related to a location.
Comments:
Notes: *Sample segment :*
DTM+132:200211131700:203'

Data Element Summary

	<u>Data Element</u>	<u>Component Element</u>	<u>Name</u>	<u>Attributes</u>
M	C507		DATE/TIME/PERIOD	M 1
M		2005	Date or time or period function code qualifier	M an..3
		132	Arrival date/time, estimated	
		133	Departure date/time, estimated	
		178	Arrival date/time, actual	
		186	Departure date/time, actual	
R		2380	Date or time or period value	C an..35
			Arrival/departure date/time	
R		2379	Date or time or period format code	C an..3
		203	CCYYMMDDHHMM	



Segment: **NAD** Name and Address
Position: 0170 (Trigger Segment)
Group: Segment Group 4 (Name and Address) Mandatory
Level: 1
Usage: Mandatory
Max Use: 1
Purpose: A segment to identify the party's which apply to the whole message

Comments:
Notes: *Sample segment :*
NAD+CF+MAE:172:20'

Data Element Summary

	Data Element	Component Element	Name	Attributes
M	3035		PARTY FUNCTION CODE QUALIFIER	M 1 an..3
			CA Carrier	
			CF Container operator/lessee	
			HR Shipping line service	
			MR Message recipient	
			MS Document/message issuer/sender	
O	C082		PARTY IDENTIFICATION DETAILS	C 1
M		3039	Party identifier	M an..35
			Company code	
O		1131	Code list identification code	C an..17
			160 Party identification	
			172 Carriers	
O		3055	Code list responsible agency code	C an..3
			20 BIC (Bureau International des Containeurs)	
			87 Assigned by carrier	
			166 US, National Motor Freight Classification Association	
			184 AU, ACOS (Australian Chamber of Shipping)	
			SMDG SMDG (Shipplanning Message Development Group)	
			Temporary code	
			ZZZ Mutually defined	
O	C058		NAME AND ADDRESS	C 1
			<i>The use of C058 is allowed to accomodate specific local requirements that exist in several ports. The use of C058 however is in general not recommended - whenever possible it is suggested to use C082 instead.</i>	
M		3124	Name and address description	M an..35
O		3124	Name and address description	C an..35
O		3124	Name and address description	C an..35
O		3124	Name and address description	C an..35
O		3124	Name and address description	C an..35
X	C080		PARTY NAME	C 1
X		3036	Party name	M an..35
X		3036	Party name	C an..35
X		3036	Party name	C an..35
X		3036	Party name	C an..35
X		3036	Party name	C an..35
X		3045	Party name format code	C an..3
X	C059		STREET	C 1
X		3042	Street and number or post office box identifier	M an..35
X		3042	Street and number or post office box identifier	C an..35
X		3042	Street and number or post office box identifier	C an..35
X		3042	Street and number or post office box identifier	C an..35



X	3164	CITY NAME	C	1	an..35
X	C819	COUNTRY SUB-ENTITY DETAILS	C	1	
X		3229 Country sub-entity name code	C		an..9
X		1131 Code list identification code	C		an..17
X		3055 Code list responsible agency code	C		an..3
X		3228 Country sub-entity name	C		an..35
X	3251	POSTAL IDENTIFICATION CODE	C	1	an..17
X	3207	COUNTRY NAME CODE	C	1	an..3



Segment: **CTA** **Contact Information**
Position: 0190 (Trigger Segment)
Group: Segment Group 5 (Contact Information) Conditional (Optional)
Level: 2
Usage: Mandatory
Max Use: 1
Purpose: A segment to identify a person or department of a message sender and/or message recipient, such as: - information contact
Comments:
Notes: *Sample segment :*
CTA+IC+:CARGO CONTROL'

Data Element Summary				
	Data	Component		<u>Attributes</u>
	<u>Element</u>	<u>Element</u>	<u>Name</u>	
R	3139		CONTACT FUNCTION CODE <i>IC</i> <i>Information contact</i>	C 1 an..3
R	C056		DEPARTMENT OR EMPLOYEE DETAILS	C 1
X		3413	Department or employee name code	C an..17
R		3412	Department or employee name <i>Contact name</i>	C an..35



Segment: **COM** Communication Contact
Position: 0200
Group: Segment Group 5 (Contact Information) Conditional (Optional)
Level: 3
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to identify a communication number of a person or department to whom communication should be directed.

Comments:

Notes: *Sample segment :*
COM+0181372453:TE'

Data Element Summary

		Data	Component		
		<u>Element</u>	<u>Element</u> <u>Name</u>	<u>Attributes</u>	
M		C076	COMMUNICATION CONTACT	M	3
M			3148 Communication address identifier Contact number.	M	an..512
M			3155 Communication address code qualifier	M	an..3
			EM Electronic mail		
			FX Telefax		
			TE Telephone		
			TL Telex		
			XF X.400 address		



Segment: **EQD** Equipment Details
Position: 0220 (Trigger Segment)
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 1
Usage: Mandatory
Max Use: 1
Purpose: A segment identifying a container, container size/type. The equipment status may be e.g. import, export, transshipment, shifter.
Comments:
Notes: *Sample segment :*
EQD+CN+MAEU5174506+4532:102:5+2+2+5'

Data Element Summary

	Data	Component				Attributes
	<u>Element</u>	<u>Element</u>	<u>Name</u>			
M	8053		EQUIPMENT TYPE CODE QUALIFIER	M	1	an..3
			BB Break bulk			
			Temporary code			
			BPP Truck and trailer combination being transported			
			CH Chassis			
			CN Container			
			RG Reefer generator			
			Power pack			
			SW Swap body			
			TE Trailer			
O	C237		EQUIPMENT IDENTIFICATION	C	1	
R		8260	Equipment identifier	C		an..17
			Marks (letters/numbers) identifying equipment. To be transmitted as they appear on the equipment.			
X		1131	Code list identification code	C		an..17
X		3055	Code list responsible agency code	C		an..3
X		3207	Country name code	C		an..3
D	C224		EQUIPMENT SIZE AND TYPE	C	1	
O		8155	Equipment size and type description code	C		an..10
			Equipment size/type code as per ISO6346 (.1 or.2, .2 preferred)			
O		1131	Code list identification code	C		an..17
			102 Size and type			
O		3055	Code list responsible agency code	C		an..3
			5 ISO (International Organization for Standardization)			
O		8154	Equipment size and type description	C		an..35
			Equipment size/type (free text)			
O	8077		EQUIPMENT SUPPLIER CODE	C	1	an..3
			1 Shipper supplied			
			2 Carrier supplied			
			5 Third party supplied			
O	8249		EQUIPMENT STATUS CODE	C	1	an..3
			1 Continental			
			2 Export			
			3 Import			
			5 Shifter			
			Restow "cell - cell"			
			6 Transshipment			
			14 Reloader			
			Restow "cell - pier - cell"			
R	8169		FULL OR EMPTY INDICATOR CODE	C	1	an..3
			4 Empty			



5
6

Full
No volume available
To be used in case of break bulk



Segment: **RFF** Reference
Position: 0230
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment identifying a reference number which relates to the equipment specified in the preceding EQD segment, such as: - container sequence number - booking number
Comments:
Notes: *Sample segment :*
RFF+BN:ROT045683'

Data Element Summary

	Data	Component			Attributes
	<u>Element</u>	<u>Element</u>	<u>Name</u>		
M	C506		REFERENCE	M	1
M		1153	Reference code qualifier	M	an..3
			AAE		Goods declaration number
			AAO		Consignee's shipment reference number
			AAY		Carrier's agent reference number
			ABT		Customs declaration number
			ABZ		Vehicle licence number
			ACD		Additional reference number
			AHI		Transport contract reference number
			AKB		Container prefix
			AKG		Vehicle Identification Number (VIN)
			AKW		Transport costs reference number
			ARJ		Personal identity card number
			ATW		Flat rack container bundle identification number
			AUA		Place of positioning reference
			BM		Bill of lading number
			BN		Booking reference number
			BST		Blockstow reference
					Temporary code
			BT		Batch number/lot number
			CN		Carrier's reference number
			CT		Contract number
			CU		Consignor's reference number
			CV		Container operators reference number
			DR		Dock receipt number
			EQ		Equipment number
					To be used in the event that an alternative equipment number is to be quoted in addition to the number in the EQD
			ER		Container/equipment receipt number
			MKS		Marks and numbers
			RE		Release number
			SQ		Equipment sequence number
			TF		Transfer number
			UCN		Unique consignment reference number
			VN		Order number (vendor)
			VT		Motor vehicle identification number
R		1154	Reference identifier	C	an..70
			Reference number		
X		1156	Document line identifier	C	an..6
X		4000	Reference version identifier	C	an..35



X

1060 Revision identifier

C

an..6



Segment: **EQN** Number of Units
Position: 0240
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 1
Purpose: A segment to specify the number of containers in one guideline that meets the same equipment details information.
Comments:
Notes: *Sample segment :
EQN+1'*

Data Element Summary				
	Data	Component	Name	Attributes
	Element	Element		
M	C523		NUMBER OF UNIT DETAILS	M 1
R		6350	Units quantity <i>Number of units</i>	C n..15
X		6353	Unit type code qualifier	C an..3



Segment: **TMD** Transport Movement Details
Position: 0250
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to indicate a Full Container Load (FCL) or a Less than Full Container Load (LCL).
Comments:
Notes: *Sample segment :
TMD+3++1'*

Data Element Summary				
	<u>Data</u>	<u>Component</u>	<u>Name</u>	<u>Attributes</u>
R	<u>Element</u>	<u>Element</u>		
R	C219		MOVEMENT TYPE	C 1
R		8335	Movement type description code	C an..3
		2	LCL/LCL = Pier/Pier = CFS/CFS	
		3	FCL/FCL = House/House = CY/CY	
		4	FCL/LCL = House/Pier = CY/CFS	
		5	LCL/FCL = Pier/House = CFS/CY	
X		8334	Movement type description	C an..35
X	8332		EQUIPMENT PLAN DESCRIPTION	C 1 an..26
O	8341		HAULAGE ARRANGEMENTS CODE	C 1 an..3
		1	Carrier	
		2	Merchant	



Segment: **DTM** Date/Time/Period
Position: 0260
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to identify a date/time related to the equipment, such as: - actual arrival/departure date/time - CSC expiration date (International Convention for Safe Containers)

Comments:
Notes: *Sample segment :*
DTM+378:200109041200:203'

Data Element Summary

	Data Component			
	<u>Element</u>	<u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	C507		DATE/TIME/PERIOD	M 1
M		2005	Date or time or period function code qualifier	M an..3
		7	Effective date/time	
		36	Expiry date	
		94	Production/manufacture date	
		171	Reference date/time	
		181	Positioning date/time of equipment	
		201	Pick-up date/time of equipment	
		371	Hydrotest date	
		376	Biannual terminal inspection date	
		377	Federal Highway Administration (FHWA) inspection date	
		378	Container Safety Convention (CSC) inspection date	
		379	Periodic inspection date	
		395	Equipment positioning date/time, estimated	
		396	Equipment positioning date/time, requested	
		397	Equipment positioning date/time, ultimate	
		400	Cargo release date/time, ultimate	
R		2380	Date or time or period value	C an..35
			Date or date/time	
R		2379	Date or time or period format code	C an..3
		102	CCYYMMDD	
		203	CCYYMMDDHHMM	



Segment: **LOC** Place/Location Identification
Position: 0270
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Required)
Max Use: 9
Purpose: A segment to identify a location or country related to the equipment, such as: -
 (final) place/port of discharge - transshipment place - place of delivery

Comments:

Notes: *Sample segment :*
LOC+11+USCHS:139:6:CHARLESTON, SC+WANDO:72:ZZZ:WANDO
TERMINAL'

Data Element Summary

	<u>Data</u>	<u>Component</u>	<u>Name</u>	<u>Attributes</u>
	<u>Element</u>	<u>Element</u>		
M	3227		LOCATION FUNCTION CODE QUALIFIER	M 1 an..3
			5 Place of departure	
			7 Place of delivery	
			8 Place of destination	
			9 Place/port of loading	
			11 Place/port of discharge	
			13 Place of transshipment	
			15 Place of transfer responsibility	
			33 Baseport of discharge	
			34 Baseport of loading	
			65 Final port or place of discharge	
			88 Place of receipt	
			98 Place of empty equipment despatch	
			147 Stowage cell	
			154 Place/location of on-hire	
			155 Place/location of off-hire	
			170 Final port of discharge	
			171 Place of destination for pre-stacking prior to stowage	
			175 Activity location	
R	C517		LOCATION IDENTIFICATION	C 1
O		3225	Location name code	C an..25
			UNLOCODE	
			<i>Stowage location (ISO format BBBRRTT) (if e3227 = 147)</i>	
O		1131	Code list identification code	C an..17
			139 Port	
O		3055	Code list responsible agency code	C an..3
			5 ISO (International Organization for Standardization)	
			Only to be used when e3227 = 147 (stowage cell)	
			6 UN/ECE (United Nations - Economic Commission for Europe)	
O		3224	Location name	C an..256
			<i>Place/location name (free text)</i>	
O	C519		RELATED LOCATION ONE IDENTIFICATION	C 1
O		3223	First related location name code	C an..25
			<i>1st related location code</i>	
O		1131	Code list identification code	C an..17
			72 Container terminal	
			261 Consignee's premises	
			262 Consignor's premises	



		263	Packing and/or unpacking facility		
		264	Storage facility		
		265	Repair facility		
		266	Marine berth		
		267	Marine wharf		
		268	Gate		
		269	Warehouse		
O		3055	Code list responsible agency code	C	an..3
		9	EAN (International Article Numbering association)		
		184	AU, ACOS (Australian Chamber of Shipping)		
		SMD	SMDG (Shipplanning Message Development Group)		
			Temporary code		
		ZZZ	Mutually defined		
O		3222	First related location name	C	an..70
			<i>1st related location name (free text)</i>		
O	C553		RELATED LOCATION TWO IDENTIFICATION	C	1
O		3233	Second related location name code	C	an..25
			<i>2nd related location code</i>		
O		1131	Code list identification code	C	an..17
		5	Facility identification		
		72	Container terminal		
		261	Consignee's premises		
		262	Consignor's premises		
		263	Packing and/or unpacking facility		
		264	Storage facility		
		265	Repair facility		
		266	Marine berth		
		267	Marine wharf		
		268	Gate		
		269	Warehouse		
O		3055	Code list responsible agency code	C	an..3
		9	EAN (International Article Numbering association)		
		184	AU, ACOS (Australian Chamber of Shipping)		
		SMD	SMDG (Shipplanning Message Development Group)		
			Temporary code		
		ZZZ	Mutually defined		
O		3232	Second related location name	C	an..70
			<i>2nd related location name (free text)</i>		
X	5479		RELATION CODE	C	1 an..3



Segment: **MEA** Measurements
Position: 0280
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment specifying a physical measurement related to the equipment, such as: - gross weight
Comments:
Notes: *Sample segment :*
MEA+AAE+AET+KGM:28000'

Data Element Summary				
	Data Element	Component Element	Name	Attributes
M	6311		MEASUREMENT PURPOSE CODE QUALIFIER	M 1 an..3
			AAE Measurement	
R	C502		MEASUREMENT DETAILS	C 1
R		6313	Measured attribute code	C an..3
			AAL Net weight	
			AAO Humidity	
			Humidity setting in percentage.	
			AAS Air flow	
			Ventilation setting in cbm/hour.	
			AAW Gross volume	
			ABJ Volume	
			AET Transport equipment gross weight	
			CD Carbondioxide	
			Carbondioxide setting in percentage	
			Temporary code	
			G Gross weight	
			MW Maximum weight	
			T Tare weight	
			ZO Oxygen	
			Oxygen setting in percentage	
X		6321	Measurement significance code	C an..3
X		6155	Non-discrete measurement name code	C an..17
X		6154	Non-discrete measurement name	C an..70
R	C174		VALUE/RANGE	C 1
M		6411	Measurement unit code	M an..3
			FTQ Cubic Feet	
			KGM Kilograms	
			LBR Pounds	
			MTQ Cubic Metres	
			PCT Percentage	
R		6314	Measurement value	C an..18
			Weight, volume or percentage.	
X		6162	Range minimum value	C n..18
X		6152	Range maximum value	C n..18
X		6432	Significant digits quantity	C n..2
X	7383		SURFACE OR LAYER CODE	C 1 an..3



Segment: **DIM** Dimensions
Position: 0290
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment specifying physical dimensions related to the equipment, such as: - gross dimensions - off standard dimension general - off standard dimension left - off standard dimension right - off standard dimension back - off standard dimension front

Comments:
Notes: *Sample segment :
DIM+13+CMT:::23'*

Data Element Summary					
M	Data Element	Component Element	Name	Attributes	
	6145		DIMENSION TYPE CODE QUALIFIER	M	1 an..3
			1 Gross dimensions <i>To be used for break bulk only</i>		
			5 Off-standard dimension front		
			6 Off-standard dimension back		
			7 Off-standard dimension right		
			8 Off-standard dimension left		
			10 External equipment dimension <i>To be used for non-ISO equipment only</i>		
			13 Off-standard dimensions height		
M	C211		DIMENSIONS	M	1
M		6411	Measurement unit code	M	an..3
			CMT Centimetres		
			INH Inches		
D		6168	Length dimension value Overall length if e6145 = 1 or 10 Overlength if e6145 = 5 or 6	C	n..15
D		6140	Width dimension value Overall width if e6145 = 1 or 10 Overwidth if e6145 = 7 or 8	C	n..15
D		6008	Height dimension value Overall height if e6145 = 1 or 10 Overheight if e6145 = 13	C	n..15



Segment: **TMP** Temperature
Position: 0310 (Trigger Segment)
Group: Segment Group 7 (Temperature) Conditional (Optional)
Level: 2
Usage: Mandatory
Max Use: 1
Purpose: A segment which identifies the transport temperature setting of the container.
Comments:
Notes: *Sample segment :*
TMP+2+048:FAH'

Only to be used when a set temperature is to be specified. When a temperature range is to be specified, the RNG segment must be used.

Data Element Summary

	Data	Component				
	<u>Element</u>	<u>Element</u>	<u>Name</u>		<u>Attributes</u>	
M	6245		TEMPERATURE TYPE CODE QUALIFIER		M	1 an..3
			2	Transport temperature		
R	C239		TEMPERATURE SETTING		C	1
R		6246	Temperature value		C	n..15
			Temperature setting			
R		6411	Measurement unit code		C	an..3
			CEL	Celsius		
			FAH	Fahrenheit		



Segment: **RNG** Range Details
Position: 0320
Group: Segment Group 7 (Temperature) Conditional (Optional)
Level: 3
Usage: Conditional (Optional)
Max Use: 1
Purpose: A segment to specify the transport temperature range setting of the container.
Comments:
Notes: *Sample segment :*
RNG+5+FAH:046:050'

Only to be used when a temperature range is to be specified. When a set temperature is to be specified, the TMP segment must be used.

Data Element Summary

	Data Component					Attributes	
	<u>Element</u>	<u>Element</u>	<u>Name</u>				
M	6167		RANGE TYPE CODE QUALIFIER			M	1 an..3
			5	Temperature range			
R	C280		RANGE			C	1
M		6411	Measurement unit code			M	an..3
			CEL	Celsius			
			FAH	Fahrenheit			
R		6162	Range minimum value			C	n..18
			Minimum temperature				
R		6152	Range maximum value			C	n..18
			Maximum temperature				



Segment: **SEL** Seal Number
Position: 0330
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment identifying a seal number related to the equipment.
Comments:
Notes: *Sample segment :*
SEL+NL5694359+CA:::MAERSK SEALAND+1'

Data Element Summary

	<u>Data Element</u>	<u>Component Element</u>	<u>Name</u>	<u>Attributes</u>
R	9308		SEAL IDENTIFIER	C 1 an..35
			<i>Seal number</i>	
O	C215		SEAL ISSUER	C 1
R		9303	Sealing party name code	C an..3
		AA	Consolidator	
		AB	Unknown	
		AC	Quarantine agency	
		CA	Carrier	
		CU	Customs	
		SH	Shipper	
		TO	Terminal operator	
X		1131	Code list identification code	C an..17
X		3055	Code list responsible agency code	C an..3
O		9302	Sealing party name	C an..35
			<i>Sealing party name (free text)</i>	
O	4517		SEAL CONDITION CODE	C 1 an..3
		1	In right condition	
		2	Damaged	
X	C208		IDENTITY NUMBER RANGE	C 1
X		7402	Object identifier	M an..35
X		7402	Object identifier	C an..35



Segment: **FTX** Free Text
Position: 0340
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to specify supplementary information related to the equipment, such as: - blockade reason - government inspection service - container loading remarks - container remarks - container order information - additional remarks concerning the container - container safety convention plate - continuous examination program (ACEP)

Comments:
Notes: *Sample segment :*
FTX+AAA+++FLOWERBULBS'
FTX+OSI++040'

Data Element Summary

	<u>Data</u> <u>Element</u>	<u>Component</u> <u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	4451		TEXT SUBJECT CODE QUALIFIER	M 1 an..3
			AAA Goods description	
			AAI General information	
			ABS Additional conditions	
			ACF Additional attribute information	
			ADZ CSC (Container Safety Convention) plate information	
			DAR Damage remarks	
			INV Invoice instruction	
			LOI Loading instruction	
			OSI Other service information	
			SIN Special instructions	
X	4453		FREE TEXT FUNCTION CODE	C 1 an..3
D	C107		TEXT REFERENCE	C 1
M		4441	Free text value code	M an..17
			<i>Reefer settings (if e4451 = OSI) :</i>	
			CLS Vents closed	
			QUA Vents one quarter open	
			HLF Vents half open	
			THR Vents three quarters open	
			FLL Vents fully open	
			025 Volume of air flow 25 cubic meters per hour	
			etc.	

Indication of construction material (if e4451 = ACF) :

Construction material code as per ISO 9897

Indication of damage condition (if e4451 = DAR) :

Condition code (see JM4/ITIGG/120)

Current equipment condition (if e4451 = ABS) :

Condition code (see JM4/ITIGG/120)

For non-running reefer (dry reefer), the correct mechanism as per JM4/272



is as follows :

e4451 = ABS

C107.e4441 = 117 (no temperature setting required)

C107.e1131 = ZZZ (mutually defined)

C107.e3055 = 184 (ACOS)

Invoice instruction (if e4451 = INV) :

Instruction code (see JM4/ITIGG/120)

Special instruction (if e4451 = SIN) :

		<i>Instruction code (mutually agreed)</i>			
O	1131	Code list identification code	C	an..17	
		130 Special handling			
		If <i>e4451</i> = INV			
		ZZZ Mutually defined			
		If <i>e4451</i> = ACF, DAR or ABS			
O	3055	Code list responsible agency code	C	an..3	
		5 ISO (International Organization for Standardization)			
		If <i>e4451</i> = ACF			
		184 AU, ACOS (Australian Chamber of Shipping)			
		If <i>e4451</i> = INV, DAR or ABS			
D	C108	TEXT LITERAL	C	1	
M	4440	Free text value	M	an..512	
		CSC problems (if <i>e4451</i> = CSC) :			
		CSC re-inspection date (CCYYMM) or			
		ACEP (if there is an acceptance sticker) or			
		NDAT (in all other cases)			
		Loading instruction (if <i>e4451</i> = LOI)			
		Free text			
		General information (if <i>e4451</i> = AAI) :			
		Free text			
		Description of goods (if <i>e4451</i> = AAA) :			
		Free text			
O	4440	Free text value	C	an..512	
O	4440	Free text value	C	an..512	
O	4440	Free text value	C	an..512	
O	4440	Free text value	C	an..512	
X	3453	LANGUAGE NAME CODE	C	1 an..3	
X	4447	FREE TEXT FORMAT CODE	C	1 an..3	



Segment: **DGS** Dangerous Goods
Position: 0370 (Trigger Segment)
Group: Segment Group 8 (Dangerous Goods) Conditional (Optional)
Level: 2
Usage: Mandatory
Max Use: 1
Purpose: A segment to identify the UN-number and the class of the dangerous goods loaded in the container.
Comments:
Notes: *Sample segment :*
DGS+IMD+3+2348+037:CEL+3+3-03'

Data Element Summary

	Data Element	Component Element	Name	Attributes
R	8273		DANGEROUS GOODS REGULATIONS CODE <i>IMD IMO IMDG code</i>	C 1 an..3
R	C205		HAZARD CODE	C 1
M		8351	Hazard identification code <i>IMDG class / sub-class number</i>	M an..7
O		8078	Additional hazard classification identifier <i>IMDG Code page number</i>	C an..7
O		8092	Hazard code version identifier <i>IMDG Code version number</i>	C an..10
O	C234		UNDG INFORMATION	C 1
R		7124	United Nations Dangerous Goods (UNDG) identifier <i>UNDG number</i>	C n4
X		7088	Dangerous goods flashpoint value	C an..8
O	C223		DANGEROUS GOODS SHIPMENT FLASHPOINT	C 1
R		7106	Shipment flashpoint value <i>Flashpoint temperature</i>	C n3
R		6411	Measurement unit code <i>CEL Celsius</i> <i>FAH Fahrenheit</i>	C an..3
O	8339		PACKAGING DANGER LEVEL CODE <i>1 Great danger</i> <i>Packing Group I</i> <i>2 Medium danger</i> <i>Packing Group II</i> <i>3 Minor danger</i> <i>Packing Group III</i>	C 1 an..3
O	8364		EMERGENCY PROCEDURE FOR SHIPS IDENTIFIER <i>EMS number</i>	C 1 an..6
O	8410		HAZARD MEDICAL FIRST AID GUIDE IDENTIFIER <i>MFAG number</i>	C 1 an..4
O	8126		TRANSPORT EMERGENCY CARD IDENTIFIER <i>TREM card number</i>	C 1 an..10
O	C235		HAZARD IDENTIFICATION PLACARD DETAILS	C 1
O		8158	Orange hazard placard upper part identifier <i>Hazard identification number, upper part</i>	C an..4
O		8186	Orange hazard placard lower part identifier <i>Hazard identification number, lower part (Substance identification number)</i>	C an4
O	C236		DANGEROUS GOODS LABEL	C 1
R		8246	Dangerous goods marking identifier	C an..4



O	8246	<i>Dangerous goods label marking 1</i> Dangerous goods marking identifier	C	an..4
O	8246	<i>Dangerous goods label marking 2</i> Dangerous goods marking identifier	C	an..4
X	8255	<i>Dangerous goods label marking 3</i> PACKING INSTRUCTION TYPE CODE	C	1 an..3
X	8325	HAZARDOUS MEANS OF TRANSPORT CATEGORY CODE	C	1 an..3
X	8211	HAZARDOUS CARGO TRANSPORT AUTHORISATION CODE	C	1 an..3



Segment: **FTX** Free Text
Position: 0380
Group: Segment Group 8 (Dangerous Goods) Conditional (Optional)
Level: 3
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to give additional information regarding dangerous goods, such as : - dangerous goods technical name.

Comments:

Notes: *Sample segment :*
FTX+AAC++PP'
FTX+AAD+++BUTYL ACRYLATES, STABILIZED'

Data Element Summary

	Data Component		Name	Attributes	
	Element	Element			
M	4451		TEXT SUBJECT CODE QUALIFIER	M	1 an..3
			AAC Dangerous goods additional information		
			AAD Dangerous goods, technical name		
X	4453		FREE TEXT FUNCTION CODE	C	1 an..3
O	C107		TEXT REFERENCE	C	1
M		4441	Free text value code	M	an..17
			MARPOL details or indication of transport of dangerous goods in limited quantities (if 4451 = AAC).		
			P Marine Pollutant		
			PP Severe Marine Pollutant		
			TLQ Transport of dangerous goods in limited quantities		
X		1131	Code list identification code	C	an..17
X		3055	Code list responsible agency code	C	an..3
O	C108		TEXT LITERAL	C	1
M		4440	Free text value	M	an..512
			Dangerous goods technical name (if e4451 = AAD)		
			Exterior placard label (if e4451 = AAC)		
O		4440	Free text value	C	an..512
O		4440	Free text value	C	an..512
O		4440	Free text value	C	an..512
O		4440	Free text value	C	an..512
X	3453		LANGUAGE NAME CODE	C	1 an..3
X	4447		FREE TEXT FORMAT CODE	C	1 an..3



Segment: **CTA** **Contact Information**
Position: 0410 (Trigger Segment)
Group: Segment Group 9 (Contact Information) Conditional (Optional)
Level: 3
Usage: Mandatory
Max Use: 1
Purpose: A segment to identify a person or department to be contacted regarding dangerous goods.
Comments:
Notes: *Sample segment :*
CTA+HE+:CHEMTREC'

Data Element Summary				
	Data	Component	Name	Attributes
	<u>Element</u>	<u>Element</u>		
R	3139		CONTACT FUNCTION CODE <i>HE Emergency dangerous goods contact</i>	C 1 an..3
R	C056		DEPARTMENT OR EMPLOYEE DETAILS	C 1
X		3413	Department or employee name code	C an..17
R		3412	Department or employee name <i>Contact name</i>	C an..35



Segment: **COM** Communication Contact
Position: 0420
Group: Segment Group 9 (Contact Information) Conditional (Optional)
Level: 4
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to specify communication details of the dangerous goods contact.
Comments:
Notes: *Sample segment :*
COM+1800873138:TE'

Data Element Summary

	<u>Data Element</u>	<u>Component Element</u>	<u>Name</u>	<u>Attributes</u>
M	C076		COMMUNICATION CONTACT	M 3
M		3148	Communication address identifier <i>Contact number</i>	M an..512
M		3155	Communication address code qualifier	M an..3
			<i>EM Electronic mail</i>	
			<i>FX Telefax</i>	
			<i>TE Telephone</i>	
			<i>TL Telex</i>	
			<i>XF X.400 address</i>	



Segment: **EQA** Attached Equipment
Position: 0430
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to identify clip-on units, such as: - generator sets
Comments:
Notes: *Sample segment :
EQA+RG+MAEG110892'*

Data Element Summary

	<u>Data</u> <u>Element</u>	<u>Component</u> <u>Element</u>	<u>Name</u>	<u>Attributes</u>
M	8053		EQUIPMENT TYPE CODE QUALIFIER	M 1 an..3
			AB Chain	
			AD Temperature recorder	
			BL Blocks	
			BR Barge	
			CH Chassis	
			CN Container	
			FSU Forked support	
			LAR Lashing rope	
			RG Reefer generator	
			Clip-on	
			RR Rail car	
			STR Strap	
			TE Trailer	
			TP Tarpaulin	
O	C237		EQUIPMENT IDENTIFICATION	C 1
R		8260	Equipment identifier	C an..17
			Equipment number	
X		1131	Code list identification code	C an..17
X		3055	Code list responsible agency code	C an..3
X		3207	Country name code	C an..3



Segment: **HAN** Handling Instructions
Position: 0440
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to specify handling instructions related to the container equipment.

Comments:

Notes: *Sample segment :*
HAN+RFR:130:184'

Data Element Summary

	Data Component		Name	Attributes	
	Element	Element			
R	C524		HANDLING INSTRUCTIONS	C	1
O		4079	Handling instruction description code <i>Code as per JM4/ITIGG/120</i>	C	an..3
O		1131	Code list identification code <i>130 Special handling</i>	C	an..17
O		3055	Code list responsible agency code <i>184 AU, ACOS (Australian Chamber of Shipping)</i>	C	an..3
O		4078	Handling instruction description <i>Handling instruction (free text)</i>	C	an..70
X	C218		HAZARDOUS MATERIAL	C	1
X		7419	Hazardous material category name code	C	an..4
X		1131	Code list identification code	C	an..17
X		3055	Code list responsible agency code	C	an..3
X		7418	Hazardous material category name	C	an..35



Segment: **TDT** Details of Transport
Position: 0460 (Trigger Segment)
Group: Segment Group 10 (Details of Transport) Conditional (Optional)
Level: 2
Usage: Mandatory
Max Use: 1
Purpose: A segment identifying the pre-carriage or on-carriage transport details by which the container will arrive before being loaded or by which the container will depart after being discharged.

Comments:

Notes: *Sample segment :*
TDT+10++3+95+:::VERACHTERT B.V.+++BGHF36'

Data Element Summary

	Data Element	Component Element	Name	Attributes
M	8051		TRANSPORT STAGE CODE QUALIFIER	M 1 an..3
			1 Inland transport	
			10 Pre-carriage transport	
			30 On-carriage transport	
O	8028		MEANS OF TRANSPORT JOURNEY IDENTIFIER	C 1 an..17
			Carrier's voyage number	
R	C220		MODE OF TRANSPORT	C 1
R		8067	Transport mode name code	C an..3
			1 Maritime Transport	
			2 Rail	
			3 Road	
			4 Air	
			8 Inland Water	
			9 Mode unknown	
X		8066	Transport mode name	C an..17
O	C228		TRANSPORT MEANS	C 1
O		8179	Transport means description code	C an..8
			Means of transport code (UN/ECE recommendation 28)	
O		8178	Transport means description	C an..17
			Type of means of transport (free text)	
O	C040		CARRIER	C 1
O		3127	Carrier identifier	C an..17
			Carrier code	
O		1131	Code list identification code	C an..17
			172 Carriers	
O		3055	Code list responsible agency code	C an..3
			20 BIC (Bureau International des Containeurs)	
			87 Assigned by carrier	
			166 US, National Motor Freight Classification Association	
			184 AU, ACOS (Australian Chamber of Shipping)	
			SMD SMDG Shippanning Message Development Group)	
			Temporary code	
			ZZZ Mutually defined	
O		3128	Carrier name	C an..35
			Carrier name (free text)	
X	8101		TRANSIT DIRECTION INDICATOR CODE	C 1 an..3
X	C401		EXCESS TRANSPORTATION INFORMATION	C 1
X		8457	Excess transportation reason code	M an..3
X		8459	Excess transportation responsibility code	M an..3
X		7130	Customer shipment authorisation identifier	C an..17



O	C222	TRANSPORT IDENTIFICATION	C	1	
O	8213	Transport means identification name identifier <i>Call sign (if e8067 = 1 and C222/e1131 = 103)</i> <i>Lloyd's Number (if e8067 = 1 and C222/e1131 = 146)</i> <i>Train ID (if e8067 = 2)</i> <i>Truck ID (if e8067 = 3)</i> <i>Air service ID (if e8067 = 4)</i> <i>Barge ID (if e8067 = 8)</i>	C		an..9
O	1131	Code list identification code 103 <i>Call sign directory</i> 146 <i>Means of transport identification</i>	C		an..17
O	3055	Code list responsible agency code 11 <i>Lloyd's register of shipping</i> ZZZ <i>Mutually defined</i>	C		an..3
O	8212	Transport means identification name <i>Vessel name or other means of transport name (free text)</i>	C		an..35
O	8453	Transport means nationality code <i>Flag of means of transport (ISO country code)</i>	C		an..3
X	8281	TRANSPORT MEANS OWNERSHIP INDICATOR CODE	C	1	an..3



Segment: **DTM** Date/Time/Period
Position: 0470
Group: Segment Group 10 (Details of Transport) Conditional (Optional)
Level: 3
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to specify date(s) and time(s) related to the on-carriage transport, such as arrival and departure date and time.
Comments:
Notes: *Sample segment :*
DTM+132:200211131700:203'

Data Element Summary

	Data Component		Attributes
	<u>Data Element</u>	<u>Component Element</u> <u>Name</u>	
M	C507	DATE/TIME/PERIOD	M 1
M		2005 Date or time or period function code qualifier	M an..3
		132 Arrival date/time, estimated	
		133 Departure date/time, estimated	
		178 Arrival date/time, actual	
		186 Departure date/time, actual	
R		2380 Date or time or period value	C an..35
		Arrival/departure date/time	
R		2379 Date or time or period format code	C an..3
		203 CCYYMMDDHHMM	



Segment: **RFF** Reference
Position: 0480
Group: Segment Group 10 (Details of Transport) Conditional (Optional)
Level: 3
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to provide alternative (non vessel operator's) voyage number and other references related to the pre-carriage or on-carriage means of transport.
Comments:
Notes: *Sample segment :
RFF+VON:005W'*

Data Element Summary

	<u>Data Element</u>	<u>Component Element</u>		<u>Attributes</u>
		<u>Element</u>	<u>Name</u>	
M	C506		REFERENCE	M 1
M		1153	Reference code qualifier	M an..3
			ATZ Ship's stay reference number	
			VM Vessel identification	
			VON Voyage number	
R		1154	Reference identifier	C an..70
			Callsign (if C506.e1153 = 'VM').	
			Alternative (non vessel operator's) voyage number (if C506.e1153 = 'VON').	
			Other reference number (if C506.e1153 = 'ATZ').	
X		1156	Document line identifier	C an..6
X		4000	Reference version identifier	C an..35
X		1060	Revision identifier	C an..6



Segment: **LOC** Place/Location Identification
Position: 0500 (Trigger Segment)
Group: Segment Group 11 (Place/Location Identification) Conditional (Optional)
Level: 3
Usage: Mandatory
Max Use: 1
Purpose: A segment identifying locations related to the transport details, such as: - place of departure

Comments:

Notes: *Sample segment :*
LOC+88+NLRTM:139:6:ROTTERDAM+DSM:262:ZZZ'

Data Element Summary

	Data	Component			Attributes
	<u>Element</u>	<u>Element</u>	<u>Name</u>		
M	3227		LOCATION FUNCTION CODE QUALIFIER	M	1 an..3
			7 Place of delivery		
			8 Place of destination		
			9 Place/port of loading		
			11 Place/port of discharge		
			13 Place of transhipment		
			88 Place of receipt		
			170 Final port of discharge		
			171 Place of destination for pre-stacking prior to stowage		
			175 Activity location		
R	C517		LOCATION IDENTIFICATION	C	1
O		3225	Location name code	C	an..25
			UNLOCODE		
O		1131	Code list identification code	C	an..17
			139 Port		
O		3055	Code list responsible agency code	C	an..3
			6 UN/ECE (United Nations - Economic Commission for Europe)		
O		3224	Location name	C	an..256
			Place/port name (free text)		
O	C519		RELATED LOCATION ONE IDENTIFICATION	C	1
O		3223	First related location name code	C	an..25
			1st related location code		
O		1131	Code list identification code	C	an..17
			72 Container terminal		
			261 Consignee's premises		
			262 Consignor's premises		
			263 Packing and/or unpacking facility		
			264 Storage facility		
			265 Repair facility		
			266 Marine berth		
			267 Marine wharf		
			268 Gate		
			269 Warehouse		
O		3055	Code list responsible agency code	C	an..3
			9 EAN (International Article Numbering association)		
			184 AU, ACOS (Australian Chamber of Shipping)		
			SMDG (Shipplanning Message Development Group)		
			Temporary code		
			ZZZ Mutually defined		
O		3222	First related location name	C	an..70



		<i>1st related location name (free text)</i>			
O	C553		RELATED LOCATION TWO IDENTIFICATION	C	1
O		3233	Second related location name code	C	an..25
		<i>2nd related location code</i>			
O		1131	Code list identification code	C	an..17
		5	Facility identification		
		72	Container terminal		
		261	Consignee's premises		
		262	Consignor's premises		
		263	Packing and/or unpacking facility		
		264	Storage facility		
		265	Repair facility		
		266	Marine berth		
		267	Marine wharf		
		268	Gate		
		269	Warehouse		
O		3055	Code list responsible agency code	C	an..3
		9	EAN (International Article Numbering association)		
		184	AU, ACOS (Australian Chamber of Shipping)		
		SMD	SMDG (Shipplanning Message Development Group)		
			Temporary code		
		ZZZ	Mutually defined		
O		3232	Second related location name	C	an..70
		<i>2nd related location name (free text)</i>			
X	5479		RELATION CODE	C	1 an..3



Segment: **NAD** Name and Address
Position: 0520
Group: Segment Group 6 (Equipment Details) Mandatory
Level: 2
Usage: Conditional (Optional)
Max Use: 9
Purpose: A segment to specify a related address or party, such as: - container operator
Comments:
Notes: *Sample segment :*
NAD+CF+MAE:172:20'

Data Element Summary

	<u>Data Element</u>	<u>Component Element</u>	<u>Name</u>	<u>Attributes</u>
M	3035		PARTY FUNCTION CODE QUALIFIER	M 1 an..3
			CA Carrier	
			CB Customs broker	
			CF Container operator/lessee	
			CG Carrier's agent	
			CN Consignee	
			CZ Consignor	
			EQ Empty container responsible party	
			FP Freight/charges payer	
			GA Road carrier	
			GT Rail carrier	
			HR Shipping line service	
			IO Insurance company	
			JB Goods collection party	
			JC Party at final place of positioning	
			MF Manufacturer of goods	
			OG Owner or lessor's surveyor	
			OH Lessee's surveyor	
			ST Ship to	
O	C082		PARTY IDENTIFICATION DETAILS	C 1
M		3039	Party identifier	M an..35
			Company code	
O		1131	Code list identification code	C an..17
			160 Party identification	
			172 Carriers	
O		3055	Code list responsible agency code	C an..3
			7 CEFIC (Conseil Europeen des Federations de l'Industrie Chimique)	
			9 EAN (International Article Numbering association)	
			10 ODETTE	
			16 US, D&B (Dun & Bradstreet Corporation)	
			20 BIC (Bureau International des Containeurs)	
			87 Assigned by carrier	
			163 US, FMC (Federal Maritime Commission)	
			166 US, National Motor Freight Classification Association	
			184 AU, ACOS (Australasian Chamber of Shipping)	
			SMDG SMDG (Shipplanning Message Development Group)	
			Temporary code	
O	C058		NAME AND ADDRESS	C 1
			<i>The use of C058 is allowed to accomodate specific local requirements that exist in several ports. The use of C058 however is in general not recommended - whenever possible it is suggested to use C082 instead.</i>	



M		3124	Name and address description	M	an..35
O		3124	Name and address description	C	an..35
O		3124	Name and address description	C	an..35
O		3124	Name and address description	C	an..35
O		3124	Name and address description	C	an..35
X	C080		PARTY NAME	C	1
X		3036	Party name	M	an..35
X		3036	Party name	C	an..35
X		3036	Party name	C	an..35
X		3036	Party name	C	an..35
X		3036	Party name	C	an..35
X		3045	Party name format code	C	an..3
X	C059		STREET	C	1
X		3042	Street and number or post office box identifier	M	an..35
X		3042	Street and number or post office box identifier	C	an..35
X		3042	Street and number or post office box identifier	C	an..35
X		3042	Street and number or post office box identifier	C	an..35
X	3164		CITY NAME	C	1 an..35
X	C819		COUNTRY SUB-ENTITY DETAILS	C	1
X		3229	Country sub-entity name code	C	an..9
X		1131	Code list identification code	C	an..17
X		3055	Code list responsible agency code	C	an..3
X		3228	Country sub-entity name	C	an..35
X	3251		POSTAL IDENTIFICATION CODE	C	1 an..17
X	3207		COUNTRY NAME CODE	C	1 an..3



Segment: **CNT** Control Total

Position: 0530

Group:

Level: 0

Usage: Conditional (Optional)

Max Use: 1

Purpose: A segment to specify the number of containers in the message, explicitly given by the sender.

Comments:

Notes: *Sample segment :*

CNT+1:1'

CNT+16:25'

Data Element Summary

	<u>Data</u>	<u>Component</u>		<u>Attributes</u>
	<u>Element</u>	<u>Element</u>	<u>Name</u>	
M	C270		CONTROL	M 1
M		6069	Control total type code qualifier	M an..3
		1	Algebraic total of the quantity values in line items in a message	
		16	Total number of equipment	
M		6066	Control total value	M n..18
			Dummy value 1 (if e6069 = 1)	
			Number of EQD segments in the message (if e6069 = 16)	
X		6411	Measurement unit code	C an..3



Segment: **UNT** Message Trailer
Position: 0540
Group:
Level: 0
Usage: Mandatory
Max Use: 1
Purpose: A service segment ending a message, giving the total number of segments in the message (including the UNH & UNT) and the control reference number of the message.
Comments:
Notes: *Sample segment :
UNT+32+100011544142'*

Data Element Summary

	Data		Component			Attributes	
	<u>Element</u>		<u>Element</u>	<u>Name</u>			
M	0074			NUMBER OF SEGMENTS IN A MESSAGE <i>Total number of segments in the message</i>	M	1	n..6
M	0062			MESSAGE REFERENCE NUMBER <i>Message reference identical to e0062 in UNH segment</i>	M	1	an..14



7. SAMPLE MESSAGE

UNH+100011544142+COPRAR:D:00B:UN:SMDG20'
BGM+121+100011544142+9+AB'
DTM+137:200211150114:203'
RFF+AAAY:58S/0220'
TDT+20+0220+1++MAE:172:20:MAERSK+++8212661:146:11:SL PRIDE:US'
RFF+VM:WDA3673'
LOC+11+NLRTM:139:6:ROTTERDAM+APMROT:72:SMD:APM TERMINALS+8200:266:ZZZ'
DTM+132:200211131700:203'
DTM+133:200211142300:203'
NAD+CF+MAE:172:20'
NAD+MS+MSKBEN:160:ZZZ'
CTA+IC+:CARGO CONTROL'
COM+0181372453:TE'
EQD+CN+MAEU5174506+4532:102:5+2+2+5'
RFF+BN:ROT045683'
TMD+3++1'
DTM+378:20010904:102'
LOC+11+USCHS:139:6:CHARLESTON, SC+WANDO:72:ZZZ:WANDO TERMINAL'
LOC+7+USMOB:139:6:MOBILE, AL'
MEA+AAE+AET+KGM:28000'
MEA+AAE+T+KGM:3000'
MEA+AAE+AAO+PCT:65'
MEA+AAE+AAS+MTQ:40'
TMP+2+048:FAH'
SEL+NL5694359+CA:::MAERSK SEALAND+1'
FTX+AAA+++FLOWERBULBS'
EQA+RG'
HAN+RFR:130:184'
TDT+10++3+95'
LOC+88+NLRTM:139:6:ROTTERDAM'
CNT+16:1'
UNT+33+100011544142'