

# Physics for mechanical engineers notes

Pradeep Janakiraman \*  
3ME department  
TU Delft, The Netherlands  
pradeepjanakiraman@student.tudelft.nl

7 November 2020

---

\*TU Delft student from 2019-2021, notes written in Quarter 2 of AY 2020-2021

# Contents

# 1 Introduction

This document is a compilation of the notes that were taken while I prepared for the ME46006, Physics for Mechanical Engineers course exam. It was written with the intention to revise as I was copying over some notes in the hopes that I would review some of the material while typing this out. The organisation of the document is simple, it starts with the necessary review of necessary mathematical prerequisites. These are mainly from the excellent resource that is [Feynman's lectures on Physics, Volume 2](#). In fact, much of the course material is covered in volume 2 and it can be used as an additional reference, as I have done. The remaining part of this document covers my summaries of the lectures in order, example problems and homework problems that were assigned.

## 2 Math and Physics preliminaries

Two basic operations in vector algebra are presented below, which are the dot product and the cross product.

$$\vec{A} \cdot \vec{B} = \begin{bmatrix} a_x & a_y & a_z \end{bmatrix} \begin{bmatrix} b_x \\ b_y \\ b_z \end{bmatrix} = S \quad (1)$$

$$\vec{A} \times \vec{B} = \begin{bmatrix} a_y b_z - b_y a_z \\ b_x a_z - a_x b_z \\ a_x b_y - b_x a_y \end{bmatrix} = \vec{V} \quad (2)$$

$\vec{A}, \vec{B}$  are vectors that live in 3-dimensions, from ?? we find that two vectors produce a scalar. While from ??, we find that two vectors produce another, third vector that is orthogonal to the first two ( $\vec{V} \perp \vec{A}, \vec{B}$ ). We also have to recall that a dot product in ?? represents a projection of the first vector onto the second vector. From these pieces of information, we can also derive the following.

$$\vec{A} \times \vec{A} = 0 \quad (3)$$

$$\vec{A} \cdot [\vec{A} \times \vec{B}] = 0 \quad (4)$$

Clearly, projecting a vector onto another vector that is orthogonal to it would lead to the zero vector. We can further write the following identities.

$$\vec{A} \cdot [\vec{B} \times \vec{C}] = [\vec{A} \times \vec{B}] \cdot \vec{C} \quad (5)$$

$$\vec{A} \times [\vec{B} \times \vec{C}] = \vec{B}(\vec{A} \cdot \vec{C}) - \vec{C}(\vec{A} \cdot \vec{B}) \quad (6)$$

### 2.1 Scalar fields and Vector fields

Firstly, a field is a physical quantity that varies in space. When those quantities are just single numbers then that field is a *scalar field*. For example, a temperature field contains the temperature at different points in space. Each point in space is characterised by a scalar value. We can then think of representing how the temperature *changes* at every point. That is which direction is the temperature increasing or decreasing in. We can imagine that there would then be another field that would represent the changing trend of temperatures at each point. Such

a field would then be a *vector field*, since the field is in three dimensional space and a change has to be quantified by a direction.

$$\Delta T = \frac{\partial T}{\partial x} \Delta x + \frac{\partial T}{\partial y} \Delta y + \frac{\partial T}{\partial z} \Delta z \quad (7)$$

The above equation makes intuitive sense. For each direction we first find the derivative function. For each point we would then have the value for the derivative by substituting the value of  $x, y, z$  into  $\frac{\partial T}{\partial x}, \frac{\partial T}{\partial y}, \frac{\partial T}{\partial z}$ . Multiplying each component of the overall derivative with the individual change in the components of the position would then result in the change of temperature between the two positions. The components of the derivative can then be made to form a vector such that,

$$\vec{\nabla} T = \left[ \frac{\partial T}{\partial x} \quad \frac{\partial T}{\partial y} \quad \frac{\partial T}{\partial z} \right] \quad (8)$$

The  $\vec{\nabla}$  vector is an operator, and when it acts on a scalar field such as  $T$  it results in a vector as seen above. ?? can then be succinctly represented as,

$$\Delta T = \vec{\nabla} T \Delta \vec{r} \quad (9)$$

The natural question to ask, would then be to see if the  $\vec{\nabla}$  operator can be used for anything else. Indeed, another two interesting applications for the  $\vec{\nabla}$  operator is called the divergence and curl of a vector field.

Divergence:

$$\vec{\nabla} \cdot \vec{h} = \frac{\partial h_x}{\partial x} + \frac{\partial h_y}{\partial y} + \frac{\partial h_z}{\partial z} \quad (10)$$

Curl:

$$\vec{\nabla} \times \vec{h} = \begin{bmatrix} \frac{\partial h_z}{\partial y} - \frac{\partial h_y}{\partial z} \\ \frac{\partial h_x}{\partial z} - \frac{\partial h_z}{\partial x} \\ \frac{\partial h_y}{\partial x} - \frac{\partial h_x}{\partial y} \end{bmatrix} \quad (11)$$

## 2.2 Interaction of div and curl operators

After going through the definitions of the divergence and curl, we can consider second derivatives. Consider the first equation, while referring to ??.

$$\vec{\nabla} \times [\vec{\nabla} T] = [\vec{\nabla} \times \vec{\nabla}] T = 0 \quad (12)$$

From this there is a useful theorem that we can use without really going through the proof.

Theorem:

If  $\nabla \times \vec{D} = 0$

There exists  $\psi$

Such that,  $\vec{D} = \nabla \psi$

Now consider a second equation that we derive from ??.

$$\vec{\nabla} \cdot [\vec{\nabla} \times \vec{h}] = 0 \quad (13)$$

Similarly, we can write another result that we can derive from ??.

Theorem:

$$\text{If } \vec{\nabla} \cdot \vec{C} = 0$$

$$\text{There exists, } \vec{\mu}$$

$$\text{Such that, } \vec{C} = \nabla \times \vec{\mu}$$

Other second derivatives we can then consider are:

$$\vec{\nabla} \cdot \vec{\nabla} T = \vec{\nabla}^2 T \quad (14)$$

$$\vec{\nabla} [\vec{\nabla} \cdot \vec{h}] = \text{A vector} \quad (15)$$

$$[\vec{\nabla} \cdot \vec{\nabla}] \vec{h} = \vec{\nabla}^2 \vec{h} \quad (16)$$

$$\vec{\nabla} \times [\vec{\nabla} \times \vec{h}] = \vec{\nabla} [\vec{\nabla} \cdot \vec{h}] - \vec{\nabla}^2 \vec{h} \quad (17)$$

$$(18)$$

We should note that:

$$\vec{\nabla}^2 = \frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + \frac{\partial^2}{\partial z^2} \quad (\text{An operator}) \quad (19)$$

## 2.3 Line and surface integral

We have already arrived at a result area when deriving the temperature difference between two points.

$$\Delta T = \vec{\nabla} T \cdot \Delta \vec{r} \quad (20)$$

However, this applies when we only consider straight paths between the initial and final points. Suppose we wanted to find the total temperature difference along some curve  $\psi$ . This curve  $\psi$ , could be broken up into tiny and approximately straight sections,  $\Delta s_1, \Delta s_2, \dots, \Delta s_n$ . Applying ?? to each of the segments would then lead to a fairly good approximation of the change in temperature along curve  $\psi$ . For an exact computation, we would then need the following conditions:




Figure 1: Line integral illustration

$$\Delta \vec{s}_i \rightarrow 0 \quad n \rightarrow \infty \quad (21)$$

We can then find write the summation of the transport equation applied to each individual segment as an integral,

$$T_{(2)} - T_{(1)} = \int_{(1)}^{(2)} \vec{\nabla} T \cdot d\vec{s} \quad (22)$$

Physically, we can represent it as in the following figure. Each part of the summation, i.e  $\vec{\nabla} T_i \cdot \Delta \vec{s}_i$  represents the projection of the grad of  $T$  onto the segment  $\Delta \vec{s}_i$ . The above result is then defined as the *line integral*. A similar concept can be extended when dealing with vector fields instead of scalar fields. Suppose that there is a vector field  $\vec{h}$  that represents the heat flow per unit area coming out of a surface. If we are then interested in the amount of heat flow that is exiting the surface, we can then consider an elemental area  $\Delta a$  just like we broke up the curve,  $\psi$  into tiny straight segments. The heat flow coming out of the tiny element can then be represented as,

$$\text{Heat flow out of elemental area} = \vec{h}_i \cdot \vec{n}_i \Delta a_i \quad (23)$$

From the above equation, we infer that for each elemental area,  $\Delta a_i$  there is a corresponding vector  $\vec{n}_i$  that is normal to the area. In addition, there is a corresponding vector  $\vec{h}_i$  that represents the heat flow vector coming out of  $\Delta a_i$ , which might not be necessarily normal to  $\Delta a_i$ . If we then impose the condition that,




Figure 2: Surface integral illustration

$$\Delta a_i \rightarrow 0 \quad (24)$$

We can write the summation of ?? applied to all segments as an integral.

$$\frac{dQ_{out,S}}{dt} = \int_S \vec{h} \cdot \vec{n} da \quad (25)$$

The above equation then refers to a *surface integral*.

## 2.4 Gauss' Theorem

Next, we can go on to write the relationship between the flux through a surface with flux through a volume. Consider the figure below. The flux through surface 1 can be written as:




Figure 3: Flux of  $\vec{C}$  through elemental cube

$$\text{Flux through (1)} = -C_x(1)\Delta y\Delta z \quad (26)$$

On the other side, the flux through surface 2 can be written as:

$$\text{Flux through (2)} = -C_x(2)\Delta y\Delta z \quad (27)$$

We then assume that this cube is very small, and that the following relationship would hold.

$$C_x(2) = C_x(1) + \frac{\partial C_x}{\partial x}\Delta x \quad (28)$$

Which implies,

$$\text{Flux through (2)} = -C_x(1)\Delta y\Delta z + \frac{\partial C_x}{\partial x}\Delta x\Delta y\Delta z \quad (29)$$

$$\text{Total flux through (2) and (1)} = -C_x(1)\Delta y\Delta z + \frac{\partial C_x}{\partial x}\Delta x\Delta y\Delta z - C_x(1)\Delta y\Delta z \quad (30)$$

$$= \frac{\partial C_x}{\partial x}\Delta V \quad (31)$$

A similar derivation can be performed for the flux through surfaces 3,4 and 5,6. We can then sum the total flux through all the surfaces as:

$$\text{Total flux} = \left[ \frac{\partial C_x}{\partial x} + \frac{\partial C_y}{\partial y} + \frac{\partial C_z}{\partial z} \right] \Delta V \quad (32)$$

$$= \vec{\nabla} \cdot \vec{C} \Delta V \quad (33)$$

Moving away from an elemental volume, larger volumes can be considered in a similar fashion by simply breaking up the large volume into many elemental volumes and applying the above result using integration. We get the following result:

$$\frac{dQ_{out,V}}{dt} = \int_V \vec{\nabla} \cdot \vec{C} dV \quad (34)$$

From the previous theorem, we already know what the flux through a surface is by employing the use of surface integrals. We then have to notice that the flux through a volume is nothing but the flux through the surface that *encloses* the volume. With this, we arrive at *Gauss' theorem*.

$$\int_S \vec{C} \cdot \vec{n} da = \int_V \vec{\nabla} \cdot \vec{C} dV \quad (35)$$

## 2.5 Circulation of a vector field and Stokes' theorem

Consider the image below. The circulation of a vector field is then defined as the summation of the tangential components of the vector field along the closed loop.




Figure 4: Circulation of  $\vec{C}$  around  $\Gamma$  visualised

$$\text{Circulation of } \vec{C} \text{ around } \Gamma = \oint_{\Gamma} \vec{C} \cdot d\vec{s} \quad (36)$$

As we have seen time and again, we can consider the circulation of a vector field around the boundary of a large surface by summing up the circulation around the boundary of elementary surfaces within the large surface in question. The circulation along of the edges of shared boundary would cancel out due to the opposing directions of circulation. Furthermore, if we constrain the elemental surfaces to be small enough, any curved surface will approximately be flat and taken as a square. From the figure below, we consider the circulation of vector field  $\vec{C}$  around a small elemental square.




Figure 5: Circulation of  $\vec{C}$  around an elemental square surface

It can also be assumed that the sides of the square is small enough such that the vector field does not change much along the length of a side. From the definition of circulation as discussed above, the circulation around this elemental square can be written as:

$$\oint_{\Gamma} \vec{C} \cdot d\vec{s} = C_x(1)\Delta x + C_y(2)\Delta y - C_x(3)\Delta x - C_y(4)\Delta y \quad (37)$$



Note that the minus signs that arise are from the direction of circulation, which is positive in the anti-clockwise direction (right hand rule). We then can write the relationship between  $C_x(1), C_x(3)$  and  $C_y(2), C_y(4)$ .

$$C_x(3) = C_x(1) + \frac{\partial C_x}{\partial y} \Delta y \quad (38)$$

$$C_y(2) = C_y(4) + \frac{\partial C_y}{\partial x} \Delta x \quad (39)$$

Substituting the above relationships into ??,

$$\oint_{\Gamma} \vec{C} \cdot d\vec{s} = \frac{\partial C_y}{\partial x} \Delta x \Delta y - \frac{\partial C_x}{\partial y} \Delta y \Delta x \quad (40)$$

$$= \left[ \frac{\partial C_y}{\partial x} - \frac{\partial C_x}{\partial y} \right] \Delta a \quad (41)$$

$$= \left[ \vec{\nabla} \times \vec{C} \right]_z \Delta a \quad (42)$$

From the figure, we notice that the  $z$ -axis is nothing but the direction that is  $\perp$  to the elemental surface. So, there is nothing special about the appearance of the  $z$ -coordinate of  $\vec{\nabla} \times \vec{C}$  appearing in the circulation derivation. We can then present *Stokes' theorem*,

$$\oint_{\Gamma} \vec{C} \cdot d\vec{s} = \int_S \left[ \vec{\nabla} \times \vec{C} \right]_n da \quad (43)$$

### 3 Lecture 1 - Electrostatics

We first define an electric field  $\vec{E}$  as the electrical force on a unit charge at position 2 due to a to a point charge  $q$  at position 1. From coloumb's law, we can then write:

$$\vec{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \vec{e}_{12} \quad (44)$$

$\vec{e}_{12}$  is the unit vector in the direction of the straight line between position 1 and 2. It should be stressed that  $E$  is a vector and as 3 components along the 3 coordinate axes. Placing a unit charge anywhere in the electric field would result in a force on the unit charge given by ??. We then consider the work done on a unit charge to move it from an initial position to another position. We know that,

$$W = - \int_b^a \vec{F} \cdot d\vec{s} \quad (45)$$

Since we are only considering unit charges however, this can be re-written as:

$$W = - \int_b^a \vec{E} \cdot d\vec{s} \quad (46)$$

The above equation is really 3 integral formulas, one for each component. Now we note that the vector field  $\vec{E}$  has some properties.

- The vector field is symmetric about the source point charge.
- The vector field points in the radial direction with the source point charge at the center

So although the integral in ?? leads to different results depending on the path from  $a$  to  $b$ , because of these two properties the integral becomes independent of the path and only depends on the positions of  $a$  and  $b$ . Because of this we can write the result of the integral as follows:

$$-\int_b^a \vec{E} \cdot d\vec{s} = \phi(b) - \phi(a) \quad (47)$$

$\phi(a, b)$  is the electric potential at points  $a$  and  $b$ . From the figure below, we can see why this would be true. If we force the path we take from  $a$  to  $b$  to pass through  $P_0$  we would get the result above. Usually  $P_0$  is taken at  $\infty$ .




Figure 6: A path moving from  $a$  to  $b$  is made to pass through  $P_0$ , which is usually taken at  $\infty$  with 0 potential

Then we can write:

$$\phi(a) = -\int_{\infty}^a \vec{E} \cdot d\vec{s} \quad (48)$$

$$= \frac{1}{4\pi\epsilon_0} \frac{q}{r_a} \quad (49)$$

It should be noted that the above holds true only when the source point charge is at the origin. If the source is not at the origin, then the new distance must be taken instead of  $r_a$ . The principle of superposition can then be invoked for the case when there is more than one source point charge and we can write:

$$\phi(1) = \sum_i \frac{1}{4\pi\epsilon_0} \frac{q_i}{r_{1i}} \quad (50)$$

$$= \frac{1}{4\pi\epsilon_0} \int_{V(2)} \frac{\rho(2)dV_2}{r_{12}} \quad (51)$$

The second equation above uses the concept of a charge density  $\rho$  that characterises many charges over a certain volume, summing up the charge density multiplied with elemental volumes would result in the total charge at the  $r_{12}$ . We can now go back to the result where the integral in ?? is path independent. We have already arrived at such a result previously in ?. It implies the following:

$$-\int_b^a \vec{E} \cdot d\vec{s} = \phi(b) - \phi(a) \quad (52)$$

$$\int_b^a -\vec{\nabla}\phi \cdot d\vec{s} = \phi(b) - \phi(a) \quad (53)$$

$$\vec{E} = -\vec{\nabla}\phi \quad (54)$$

However, we have already gone through the properties of double derivatives in ?? and using that relationship, we can define:

$$\vec{\nabla} \times \vec{E} = 0 \quad (55)$$

Which is one of Maxwell's equations for electrostatics.