

# Semidefinite Programming, Computational Intelligence, Lecture 10

by Sergei Savin

Spring 2021

- Semidefinite Programming (SDP)
  - ▶ General form
  - ▶ Multiple LMI
  - ▶ SDP decision variable
- Example 1: Continuous Lyapunov equation as an SDP/LMI
- Example 2: Discrete Lyapunov equation as an SDP/LMI
- Example 3: LMI Controller design for continuous LTI
- How to describe an ellipsoid
- Volume of an ellipsoid
- Inscribed ellipsoid algorithms
- Homework

# SEMIDEFINITE PROGRAMMING (SDP)

## General form

General form of a semidefinite program is:

$$\begin{aligned} & \underset{\mathbf{x}}{\text{minimize}} && \mathbf{c}^\top \mathbf{x}, \\ & \text{subject to} && \begin{cases} \mathbf{G} + \sum \mathbf{F}_i x_i \preceq 0, \\ \mathbf{A}\mathbf{x} = \mathbf{b}. \end{cases} \end{aligned} \tag{1}$$

where  $\mathbf{F}_i \succeq 0$  and  $\mathbf{G} \succeq 0$  (meaning they are positive semidefinite).

Constraint  $\mathbf{G} + \sum \mathbf{F}_i x_i \preceq 0$  is called *linear matrix inequality* or *LMI*.

# SEMIDEFINITE PROGRAMMING (SDP)

## Multiple LMI

SDP can have several LMIs. Assume you have:

$$\begin{cases} \mathbf{G} + \sum \mathbf{F}_i x_i \preceq 0 \\ \mathbf{D} + \sum \mathbf{H}_i x_i \preceq 0 \end{cases} \quad (2)$$

This is equivalent to:

$$\begin{bmatrix} \mathbf{G} & \mathbf{0} \\ \mathbf{0} & \mathbf{D} \end{bmatrix} + \sum \begin{bmatrix} \mathbf{F}_i & \mathbf{0} \\ \mathbf{0} & \mathbf{H}_i \end{bmatrix} x_i \preceq 0 \quad (3)$$

# SEMIDEFINITE PROGRAMMING (SDP)

## SDP decision variable

Sometimes it is easier to directly think of semidefinite matrices as of decision variables. This leads to programs with such formulation:

$$\begin{array}{ll} \underset{\mathbf{X}}{\text{minimize}} & f(\mathbf{X}), \\ \text{subject to} & \begin{cases} \mathbf{X} \preceq 0, \\ \mathbf{g}(\mathbf{X}) = \mathbf{0}. \end{cases} \end{array} \quad (4)$$

where cost and constraints should adhere to SDP limitations.

# Ex. 1: CONTINUOUS LYAPUNOV EQ. AS SDP/LMI

## Mathematical formulation

In control theory, Lyapunov equation is a condition of whether or not a continuous LTI system  $\dot{\mathbf{x}} = \mathbf{A}\mathbf{x}$  is stabilizable:

$$\begin{cases} \mathbf{A}^\top \mathbf{P} + \mathbf{P}\mathbf{A} + \mathbf{Q} = 0 \\ \mathbf{P} \succeq 0 \\ \mathbf{Q} \succeq 0 \end{cases} \quad (5)$$

where decision variable is  $\mathbf{P}$ . This can be represented as an SDP:

$$\begin{aligned} & \underset{\mathbf{P}}{\text{minimize}} && 0, \\ & \text{subject to} && \begin{cases} \mathbf{P} \succeq 0, \\ \mathbf{A}^\top \mathbf{P} + \mathbf{P}\mathbf{A} + \mathbf{Q} = 0. \end{cases} \end{aligned} \quad (6)$$

# Ex. 1: CONTINUOUS LYAPUNOV EQ. AS SDP/LMI

## Code

```
0 n = 7; A = randn(n, n) - 3*rand*eye(n);
  Q = eye(n);
2
  cvx_begin sdp
4      variable P(n, n) symmetric
      minimize 0
6      subject to
          P >= 0;
          A'*P + P*A + Q <= 0;
8      cvx_end
10
11 if strcmp(cvx_status, 'Solved')
12     [eig(A), eig(A*P + P*A' + Q), eig(P)]
13 else
14     eig(A)
15 end
```

## Ex. 2: DISCRETE LYAPUNOV EQ. AS SDP/LMI

### Mathematical formulation

In control theory, Discrete Lyapunov equation is a condition of whether or not a discrete LTI system  $\mathbf{x}_{i+1} = \mathbf{A}\mathbf{x}_i$  is stabilizable:

$$\begin{cases} \mathbf{A}^\top \mathbf{P} \mathbf{A} - \mathbf{P} + \mathbf{Q} = 0 \\ \mathbf{P} \succeq 0 \\ \mathbf{Q} \succeq 0 \end{cases} \quad (7)$$

where decision variable is  $\mathbf{P}$ . This can be represented as an SDP:

$$\begin{aligned} & \underset{\mathbf{P}}{\text{minimize}} && 0, \\ & \text{subject to} && \begin{cases} \mathbf{P} \succeq 0, \\ \mathbf{A}^\top \mathbf{P} \mathbf{A} - \mathbf{P} + \mathbf{Q} = 0. \end{cases} \end{aligned} \quad (8)$$



## Ex. 2: DISCRETE LYAPUNOV EQ. AS SDP/LMI

### Code

```
0 n = 7; A = 0.35*randn(n, n);
  Q = eye(n);
2
  cvx_begin sdp
4      variable P(n, n) symmetric
      minimize 0
6      subject to
          P >= 0;
          A'*P*A - P + Q <= 0;
8      cvx_end
10
11 if strcmp(cvx_status, 'Solved')
12     [abs(eig(A)), eig(A'*P*A - P), eig(P)]
13 else
14     abs(eig(A))
15 end
```

## Ex. 3: FTS FOR CONTINUOUS LTI

### Mathematical formulation

For an LTI system of the form  $\dot{\mathbf{x}} = \mathbf{A}\mathbf{x} + \mathbf{B}\mathbf{u}$  there is an LMI condition to determine if it can be stabilized:

$$\begin{cases} \mathbf{A}\mathbf{P} + \mathbf{P}\mathbf{A}^\top + \mathbf{B}\mathbf{L} + \mathbf{L}\mathbf{B}^\top + \mathbf{Q} = 0 \\ \mathbf{P} \succ 0 \\ \mathbf{Q} \succ 0 \end{cases} \quad (9)$$

where decision variables are  $\mathbf{P}$  and  $\mathbf{L}$ .

This gives as a direct way to calculate linear feedback controller  $\mathbf{u} = \mathbf{K}\mathbf{x}$  (note the sign!) gains:

$$\mathbf{K} = \mathbf{L}\mathbf{P}^{-1} \quad (10)$$

## Ex. 3: FTS FOR CONTINUOUS LTI, CODE

```
0  n = 5; m = 2;
   A = randn(n, n);
2  B = randn(n, m);
   Q = eye(n)*0.1;
4  cvx_begin sdp
      variable P(n, n) symmetric
6      variable Z(m, n)

      minimize 0
      subject to
10         P >= 0;
           A*P + P*A' + B*Z + Z'*B' + Q <= 0;
12 cvx_end
   P = full(P);
14 Z = full(Z);
   K_LMI = Z*pinv(P);
16
   disp('K_LMI eig:')
18 eig(A + B*K_LMI)
```

# HOW TO DESCRIBE AN ELLIPSOID

## Unit sphere transformation

Let us first remember how we describe a unit sphere:

$$\mathcal{S} = \{\mathbf{x} : \|\mathbf{x}\| \leq 1\} \quad (11)$$

An ellipsoid can be seen as a linear transformation of a unit sphere:

$$\mathcal{E} = \{\mathbf{Ax} + \mathbf{b} : \|\mathbf{x}\| \leq 1\} \quad (12)$$

# HOW TO DESCRIBE AN ELLIPSOID

## A dual description

Let us introduce a change of variables  $\mathbf{z} = \mathbf{A}\mathbf{x} + \mathbf{b}$ . Assuming  $\mathbf{A}$  is invertible, we get:

$$\mathbf{x} = \mathbf{A}^{-1}(\mathbf{z} - \mathbf{b}) \quad (13)$$

So, we can describe the exact same ellipsoid using an alternative formula:

$$\mathcal{E} = \{\mathbf{z} : \|\mathbf{B}\mathbf{z} + \mathbf{c}\| \leq 1\} \quad (14)$$

where  $\mathbf{B} = \mathbf{A}^{-1}$  and  $\mathbf{c} = -\mathbf{A}^{-1}\mathbf{b}$ .

# VOLUME OF AN ELLIPSOID

## Part 1

For an ellipsoid of the form

$$\mathcal{E} = \{\mathbf{A}\mathbf{x} + \mathbf{b} : \|\mathbf{x}\| \leq 1\} \quad (15)$$

the "bigger" the  $\mathbf{A}$ , the bigger the ellipsoid. This concept can be made concrete by talking about the determinant of  $\mathbf{A}$ .

Thus, maximizing the volume of this ellipsoid is the same as maximizing  $\det(\mathbf{A})$ . Or, it is the same as *minimizing* the  $\det(\mathbf{A}^{-1})$ , since  $\det(\mathbf{A}^{-1}) = 1/\det(\mathbf{A})$ .

# VOLUME OF AN ELLIPSOID

## Part 2

For an ellipsoid of the form

$$\mathcal{E} = \{\mathbf{z} : \|\mathbf{B}\mathbf{z} + \mathbf{c}\| \leq 1\} \quad (16)$$

the "bigger" the  $\mathbf{B}$ , the *smaller* the ellipsoid. We can make it obvious by thinking that increasing  $\mathbf{B}$  leaves less room for valid  $\mathbf{z}$ , and it is the volume of valid  $\mathbf{z}$  that makes the volume of the ellipsoid in this case.

This concept can be made concrete by talking about the determinant of  $\mathbf{B}$ . Thus, maximizing the volume of this ellipsoid is the same as *minimizing*  $\det(\mathbf{B})$ . Or, it is the same as *maximizing* the  $\det(\mathbf{B}^{-1})$ .

Continue with slides from Convex Optimization — Boyd & Vandenberghe. Follow the link:

## 8. Geometric problems



Implement both examples from page 2 of the LMI CVX documents.

Lecture slides are available via Moodle.

You can help improve these slides at:

[github.com/SergeiSa/Computational-Intelligence-Slides-Spring-2021](https://github.com/SergeiSa/Computational-Intelligence-Slides-Spring-2021)



Check Moodle for additional links, videos, textbook suggestions.