

# MATH 8803: Nonlinear Dispersive Equations

Frank Qiang  
Instructor: Gong Chen

Georgia Institute of Technology  
Spring 2025

# Contents

<b>1</b>	<b>Jan. 6 — Introduction to Dispersion</b>	<b>2</b>
1.1	Introduction to Dispersion . . . . .	2
1.2	Fourier Transform and the Free Schrödinger Equation . . . . .	3
1.3	Sobolev Spaces . . . . .	4

# Lecture 1

## Jan. 6 — Introduction to Dispersion

### 1.1 Introduction to Dispersion

**Definition 1.1.** An evolution equation is *dispersive* if when no boundary conditions are imposed (e.g. on  $\mathbb{R}^n$ ), its wave solutions spread out in space as they evolve in time.

**Example 1.1.1.** Two classic examples of dispersive equations are:

- The *Schrödinger equation*:  $iu_t + \Delta u = 0$ .
- The *Airy (linearized KdV) equation*:  $u_t + u_{xxx} = 0$ .

**Remark.** Consider the equation  $u_t + p(\partial_x)u = 0$ , where  $p$  is a polynomial, and a plane-wave solution

$$u(t, x) = e^{i(kx - \omega t)} = e^{ik(x - (\omega/k)t)}.$$

Here  $k$  is the *wave number* or *space frequency*, and  $\omega$  is the *(time) frequency*. Plugging the plane-wave solution into the equation, we obtain the relation  $\omega(k) = -ip(ik)$ , i.e.

$$\frac{\omega(k)}{k} = \frac{1}{ik}p(ik).$$

The above equation is known as the *dispersive relation*. This gives the traveling speed of the plane-wave solution with wave number  $k$ , which is called the *phase velocity*.

**Example 1.1.2.** The following are some examples of dispersive relations:

- For the *linear advection equation*  $u_t + cu_x = 0$  with  $c \in \mathbb{R}$ , one can compute that  $\omega/k = c$ .
- For the Schrödinger equation  $iu_t + \frac{1}{2}\Delta u = 0$ , we have  $\omega/k = k/2 \in \mathbb{R}$ .

In this case of the Schrödinger equation, plane waves with large wave number (large space frequency) travel faster than low-frequency waves.

**Remark.** In general, dispersion means that different frequency plane waves travel at different speeds.

**Remark.** Given initial data  $u_0$ , we can write using the Fourier transform that

$$u_0 = \int \widehat{u}_0(k) e^{ikx} dk.$$

Then we get the solution  $u$  as

$$u(t, x) = \int \widehat{u}_0(k) e^{ik(x - (\omega(k)/k)t)} dk.$$

**Example 1.1.3.** In the case of the linear advection equation, we obtain the solution as

$$u(t, x) = \int \widehat{u}_0(k) e^{ik(x-ct)} dk = u_0(x - ct).$$

For the Schrödinger equation, we instead have the solution

$$u(t, x) = \int \widehat{u}_0(k) e^{ik(x-(k/2)t)} dk.$$

Since different  $k$  travels at different speeds, the original profile quickly spreads out.

**Exercise 1.1.** Calculate the dispersive relation  $\omega/k$  for the linearized KdV equation  $u_t + u_{xxx} = 0$ .

**Example 1.1.4.** The *KdV equation* is given by

$$\partial_t u + \partial_{xxx} u + 6u \partial_x u = 0.$$

This equation is used to model shallow water surfaces, and is a nonlinear dispersive equation. Russell observed a great bump of water in a channel that traveled for a long time and kept its shape. This is due to the nonlinear effects in the KdV equation, and these effects are called *solitons*.

**Definition 1.2.** A *soliton* is a self-reinforcing solitary wave (a wave packet or pulse) that maintains its shape while traveling at a constant speed.

## 1.2 Fourier Transform and the Free Schrödinger Equation

Consider the following free Schrödinger equation:

$$\begin{cases} i\partial_t \psi + \frac{1}{2}\Delta \psi = 0, \\ \psi|_{t=0} = \psi_0. \end{cases}$$

We will solve this equation using the *Fourier transform*

$$\widehat{f}(\xi) = \int_{\mathbb{R}^d} e^{-ix \cdot \xi} f(x) dx.$$

Note that one can recover  $f$  from its Fourier transform via the *inversion formula*

$$f(x) = \frac{1}{(2\pi)^d} \int_{\mathbb{R}^d} e^{ix \cdot \xi} \widehat{f}(\xi) d\xi.$$

**Exercise 1.2.** Check that  $(\partial_{x_j} f)^\wedge = i\xi_j \widehat{f}$ .

Applying the Fourier transform to the free Schrödinger equation, one has

$$i\partial_t \psi + \frac{1}{2}\Delta \psi = 0 \quad \xrightarrow{\text{F.T.}} \quad i\partial_t \widehat{\psi} - \frac{1}{2}|\xi|^2 \widehat{\psi} = 0$$

and initial condition  $\widehat{\psi}(0, \xi) = \widehat{\psi}_0(\xi)$ . So for fixed  $\xi$ , we have an ODE, so we can solve the equation via

$$\widehat{\psi}(t, \xi) = e^{-i|\xi|^2 t/2} \widehat{\psi}_0(\xi).$$

Now by applying the inverse Fourier transform, we obtain the solution

$$\psi(t, x) = \frac{1}{(2\pi)^d} \int e^{ix\xi} \widehat{\psi}(t, \xi) d\xi = \frac{1}{(2\pi)^d} \int e^{ix\xi} e^{-i|\xi|^2 t/2} \widehat{\psi}_0(\xi) d\xi.$$

Recalling Plancherel's theorem that  $\|f\|_{L^2} = C\|\widehat{f}\|_{L^2}$  (for a constant  $C$  independent of  $f$ ), we obtain

$$\|\psi(t, x)\|_{L^2} = C\|\widehat{\psi}(t, \xi)\|_{L^2} = C\|\widehat{\psi}(0, \xi)\|_{L^2} = \|\psi(0, x)\|_{L^2} = \|\psi_0(x)\|_{L^2},$$

where the second equality follows by noticing that  $e^{-i|\xi|^2 t/2}$  has modulus 1. This shows that the linear Schrödinger evolution preserves the  $L^2$  norm of the solution.

**Exercise 1.3.** Compute that

$$\frac{d}{dt} \int_{\mathbb{R}^d} |\psi(t, x)|^2 dx = 0.$$

This is an alternative way to show that the  $L^2$  norm of the solution is preserved.

## 1.3 Sobolev Spaces

**Definition 1.3.** The *Sobolev spaces*  $H^\gamma = W^{\gamma,2}$  for  $\gamma \in \mathbb{R}$  are defined via the norm

$$\|f\|_{H^\gamma} = \left( \int_{\mathbb{R}^d} (1 + |\xi|^2)^\gamma |\widehat{f}(\xi)|^2 d\xi \right)^{1/2}.$$

The *homogeneous Sobolev spaces*  $\dot{H}^\gamma$  are defined by the norm

$$\|f\|_{\dot{H}^\gamma} = \left( \int_{\mathbb{R}^d} |\xi|^{2\gamma} |\widehat{f}(\xi)|^2 d\xi \right)^{1/2}.$$

**Remark.** If  $\gamma \in \mathbb{N}$  and  $d = 1$ , then

$$\|f\|_{H^\gamma} \sim \sum_{m=0}^{\gamma} \|\partial_x^m f\|_{L^2}.$$

In particular, this means that  $f \in H^\gamma$  if and only if  $\partial_x^m f \in L^2$  for all  $m \leq \gamma$ .

**Exercise 1.4.** Check that if  $f_\lambda(x) = f(\lambda x)$ , then  $\widehat{f}_\lambda(\xi) = \lambda^{-d} \widehat{f}(\xi/\lambda)$ .

**Remark.** In the Sobolev spaces, this means that (change variables  $\eta = \xi/\lambda$  for the last equality)

$$\|f_\lambda\|_{\dot{H}^\gamma} = \left( \int_{\mathbb{R}^d} |\xi|^{2\gamma} |\widehat{f}_\lambda(\xi)|^2 d\xi \right)^{1/2} = \left( \int_{\mathbb{R}^d} |\xi|^{2\gamma} |\lambda^{-d} \widehat{f}(\xi/\lambda)|^2 d\xi \right)^{1/2} = \lambda^{\gamma-d/2} \|f\|_{\dot{H}^\gamma}.$$

**Lemma 1.1.** In the Schrödinger equation,  $\|\psi(t)\|_{H^\gamma} = \|\psi_0\|_{H^\gamma}$  and  $\|\psi(t)\|_{\dot{H}^\gamma} = \|\psi_0\|_{\dot{H}^\gamma}$  for all  $t$  and  $\gamma$ .

*Proof.* We can compute that

$$\|\psi(t)\|_{\dot{H}^\gamma}^2 = \int_{\mathbb{R}^d} |\xi|^{2\gamma} |\widehat{\psi}(t, \xi)|^2 d\xi = \int_{\mathbb{R}^d} |\xi|^{2\gamma} |e^{-i|\xi|^2 t/2} \widehat{\psi}_0(\xi)|^2 d\xi = \int_{\mathbb{R}^d} |\xi|^{2\gamma} |\widehat{\psi}_0(\xi)|^2 d\xi = \|\psi_0\|_{\dot{H}^\gamma}^2.$$

The same argument works for the  $H^\gamma$  case after replacing  $|\xi|^{2\gamma}$  with  $(1 + |\xi|^2)^\gamma$ . □