

Compiling storm :

Unzip shared apache-0.9.2-incubating.zip. Run :

```
cd directory
mvn clean install -DskipTests=true
cd /storm-dist/binary
mvn package -DskipTests=true
```

Setting up Storm in the cluster :

- The required files for running storm are “apache-storm-0.9.2-incubating.zip”, move_storm_files.sh, config_storm.sh, Fault_injector_iterate.py, storm.yaml, timeout_compute.py
- apache-storm-0.9.2-incubating.zip will be located inside the unzipped folder (shared) under /apache-storm-0.9.2-incubating/storm-dist/binary/target/apache-storm-0.9.2-incubating.zip
- All the other files are zipped and attached (storm-starter-0.9.2-incubating-jar-with-dependencies.jar is also required but it can be obtained by compiling storm starter after unzipping “apache-0.9.2-incubating.zip”)
- Change the paths of some of the files accordingly in move_storm_files.sh
- Use the script ./move_storm_files.sh after all VMs have been started

move_storm_files.sh :

Transfers all files to all running cluster VM's.

- apache-storm-0.9.2-incubating.zip is stored in /tmp/ directory in each VM
- config_storm.sh, storm.yaml, timeout_compute.py are also transferred to /tmp/ directory in each VM
- storm-starter-0.9.2-incubating-jar-with-dependencies.jar is transferred to /home/vignesh in nimbus. This can be modified accordingly in move_storm_files.sh
- Fault_injector_iterate.py is also transferred to /home/vignesh in nimbus. The destination can be modified accordingly in move_storm_files.sh

config_storm.sh :

Log in to each cluster VM. At each VM do the following to setup storm :

- /tmp/config_storm.sh - would setup the new version of storm and a link to the executable would be created in /home/vignesh in the VM

timeout_compute.py :

The would remain in /tmp/. It can be relocated to /app/home/storm (Storm home directory) if required. This step is optional. All slaves currently already contain the latest version of timeout_compute.py

Fault injector iterate.py :

It is a multi purpose script. Word count topology currently takes in 4 arguments. Before starting the python script, the path to “storm” executable and “storm-starter-0.9.2-incubating-jar-with-dependencies.jar” must be set inside the subprocess statement in the script. If all previous steps are followed, both these files will be located in /home/vignesh in nimbus.

Word count topology takes four arguments :

1st argument : Topology name (which is “WordCount” currently)

2nd argument : Current rate

3rd argument : str(1) or str(0) to enable or disable adaptive timeout respectively

4th argument : sample_size which is related to the message drop probability as msg drop prob = 1/sample_size. If sample_size is ignored or set to 0, then no messages are dropped.

Setting the adaptive timeout mode :

The adaptive timeout mode can be set by setting the string Adaptive_timeout_mode in Word_count_topology.java accordingly :

Current supported modes :

NORMAL : Constant timeout value of 30 sec

END_TO_END : End_to_end mode, “End_to_End.java” is activated.

QUEUEING MODEL <Submodelname> : This represents a class of Queuing model based timeouts. The name can be arbitrary but is must have a prefix “QUEUEING MODEL” to active Queueing_model.java. For example mode can be “QUEUEING MODEL MM1” or “QUEUEING MODEL G/G/1” and so on. The mode value is passed to the Queueing_model object and set to the attribute called mode in Queueing_model.java.

Current Supported Timeout Modes :

NORMAL

END_TO_END

QUEUEING MODEL MM1

QUEUEING MODEL Heavy Traffic

Output files :

Currently files would be output only for the NORMAL and END_TO_END modes. NORMAL mode would output the total latency and statistics. END_TO_END mode would output total latency, statistics, tick tuple files as well. The Word_Count_topology.java defines a string called topology_name which defines the output_folder name. Currently it is set to “Word_count_topology”. So the output files are located inside /app/home/storm/Word_count_topology. The folder would contain sub folders defined by the spout rate, sample_size, tweet keyword and whether the adaptive timeout is enabled or not. These folders can be named as desired by setting the topology-info string in Word_Count_topology.java.