

Optical Properties of Gain incorporating Photonic Resonators



by
AHMAD BILAL
CIIT/FA15-BPH-019/ISB

BS Thesis
In
Physics

COMSATS University Islamabad
Islamabad - Pakistan

January, 2019



COMSATS University Islamabad

Optical Properties of Gain incorporating Photonic
Resonators

A Thesis Presented to

COMSATS University Islamabad

In partial fulfillment

of the requirement for the degree of

Bachelor of Science in Physics

by

Ahmad Bilal
CUI/FA15-BPH-019/ISB

Spring, 2019

Optical Properties of Gain incorporating Photonic Resonators

A Under Graduate Thesis submitted to the Department of Physics as partial fulfillment of the requirement for the award of Degree of BS (Physics).

Name	Registration Number
Ahmad Bilal	CUI/FA15-BPH-019/ISB

Supervisor:

Dr. Ahmer Naweed,
Associate Professor,
Department of Physics,
COMSATS University Islamabad (CUI),
January, 2019.

Final Approval

This thesis titled

Optical Properties of Gain incorporating Photonic Resonators

By

ar *Ahmad Bilal*

CIIT/FA15-BPH-019/ISB

Has been approved

For the COMSATS University Islamabad

External Examiner: _____

Supervisor: _____

Dr. Ahmer Naweed

Associate Professor, Dept. of Physics

COMSATS University Islamabad

HoD: _____

Dr. Sajid Qamar

Professor, Dept. of Physics

COMSATS University Islamabad

Declaration

I **Ahmad Bilal** (CIIT/FA15-BPH-019/ISB) hereby declare that this project neither as a whole nor as a part there of has been copied out from any source. It is further declared that I have developed this thesis and the accompanied report entirely on the basis of my personal efforts made under the sincere guidance of my supervisors. No portion of the work presented in this report has been submitted in support of any other degree of qualification of this or any other University or Institute of learning, if found I shall stand responsible.

Date:

Ahmad Bilal
CIIT/FA15-BPH-019/ISB

Certificate

It is certified that Ahmad Bilal (Registration No. CIIT/FA156-BPH-019/ISB) has carried out all the work related to this thesis under my supervision at the Department of Physics, COMSATS University Islamabad and the work fulfills the requirement for award of BS degree.

Date: Jan, 2019

Supervisor:

Dr. Ahmer Naweed
Associate Professor, Department of Physics

Head of Department:

Dr. Sajid Qamar
Department of Physics

Dedication

This thesis is dedicated to my mother who brought me up all by herself, motivated me to always persue my dreams and made me the gentleman I am today.

Abstract

Since long, electronic integrated circuits have dominated our modern technology. Now with the dawn of photonics, which is basically using integrated circuits made up using optics, its not far that our modern technology takes a new toll and slide into a new generation of digital devices. Basically, Photonics is the technology of generating and harnessing light, and other form of radiant energy whose quantum unit is a photon. These can be used in multiple applications , to explore the vastness of the Universe, cure serious and unknown diseases and even help in forensics to solve difficult crime cases.

In this project, we extended the research on optical ring resonators for such mediums in which there is gain. First we studied normally the optical properties of passive resonators and measured the effects of EIT and EIA in them (details later discussed). Then we moved over focus on active resonators varrying different parameters to acheive EIT and EIA in gain incorporating photonic resonators which have extensive amount of applications. The main focus for this project was to model the characteristics and properties of active resonators and compare it with the results of passive resonators. Due to the gain property of active resonators, similar effects can be seen here as in passive resonators but without losses involved. The main idea was to establish a photonic device that could work efficiently as passive resonators and also have more output.

Light is a beautiful thing, it makes us see things, but what if it also starts to help us organize our data, compute our equations, play our music, record our documents

and basically do everything what a modern digital device, built on electronics, is capable of doing? I guess we'll find out!

*Indeed, in the creation of the heavens,
and the earth and the alternation of
the night and the day, are signs for
those of understanding.*

The Noble Quran [3:190]

Acknowledgement

In the name of Allah, who is the most beneficent and merciful. I would start off this extensive documentation with a quote from Carl Sagan, one of the greatest science educator, who created enough enthusiasm and curiosity in me to pursue my career in Physics. He said, "*Somewhere, something incredible is waiting to be known*". This is one of the reason I chose to be a student of physics, it inspires me to search for the unknown clues that are hidden in the very fabric of reality. Physics gave mankind the power to dominate their world and use the best of nature for their benefit.

Since childhood, I had always been fascinated by computers and gadgets. Having the background of engineers in my family, I almost ended up joining the computer engineering in High School. But the curiosity inside me had made me a star gazer. So I had questions about how they get where they are, and what are they made of? These questions were those which made me switch my field to Physics which is a science of never-ending curiosity. In this process, a lot of people are included some directly and some indirectly, most of which is my family, because their never-ending support had made me pursue my dreams.

I would personally like to thank my supervisor in BS project, Dr. A. Naweed, who helped me through thick and thin to complete this project and also kept me motivated enough to continue my research in field of photonics. I would like to

thank my batch counselor Dr. A. H. Mujtaba, who's support and teachings made us all work harder and harder for the progression of science. Also there is a big role of Ms. Zarqa in my motivation for this project. She not only recommended me to Dr. Naweed, but she is also my mental health counselor when I am in dire need of help. I would like to thank my peers in this, because the support and love I get from them is unmeasureable. Then again I would like to thank my family and especially my mother, who never asked me about my GPA and anything and always said, "if you love what you are studying, only then you can get true learning."

In the end, it is important to know that Knowledge is a never ending process, and Physics is such a beautiful field that every time I learn a new concept about the universe, it feels like I have been born again.

Ahmad B. Yousafzai

Islamabad, Jan 2019

Contents

Dedication	vii
Abstract	viii
Acknowledgement	x
1 Introduction	1
1.1 Resonators	3
1.1.1 Explanation	3
1.2 Optical Resonators	4
1.3 Different Types of Optical Resonators	5
1.3.1 Fabry-Perot Resonator	5
1.3.2 Gires-Tournois	5
1.4 Micro Resonators	5
1.4.1 Different Geometries	6
1.5 Electromagnetically Induced Transparency and Induced Absorption (EIT and EIA)	7
1.6 Aim and Objective	8
References	9
2 Fundamental Characteristics of Optical Resonators	10
2.1 The Fabry-Perot Interferometer	10
2.1.1 Theory of Fabry-Perot interferometer	11
2.1.2 Effective Phase	13
2.1.3 Phaser plots	13
2.1.4 Finesse, Q-factor	14
2.2 Gain incorporation in Resonators	15
2.2.1 Beer's Law	16
2.2.2 Beer's law study as gain	16
2.2.3 Gain medium	17
2.3 Ring Geometry Resonators	17
2.3.1 All-Pass Ringresonator	18
2.3.2 Add-Drop Ringresonator	21
2.4 Coupled Ringresonator	23
2.4.1 Coupled resonator induced transparency and induced absorption . .	24
References	25

3	Electromagnetically Induced Transparency and Absorption	26
3.1	EIT in Atoms	26
3.1.1	Two level Atoms	26
3.2	EIT in ring resonators	26
3.3	EIT in Coupled resonators(CRIT)	27
3.4	CRIT with gain	27
3.5	Results	27
3.6	EIA concepts	28
3.6.1	EIA in atoms	28
3.6.2	EIA Quantum phenomena	28
3.7	EIA in resonators	29
3.7.1	Coupled resontors induced Absorption	29
3.8	CRIA with gain	29
4	Composite Resonator Systems	31
4.1	Coupled resontaor with Gain medium	31
4.1.1	Gain element	31
4.2	Calculation/Equations	31
4.2.1	For single	32
4.2.2	For coupled	32
4.2.3	For triple	32
4.3	Coupling Regimes	33
4.4	Gain controlled EIT and EIA	33
5	Gain Incorporation	34
6	Conclusion	35
A	Abrevations	37

List of Figures

1.1	Illustration of a basic optical cavity.[4]	5
1.2	Different geometries of microresonators.[3]	6
2.1	Illustrated energy diagram of a simple Fabry-Perot resonator	10
2.2	Transmitted and reflected field of an asymmetric Fabry-Perot resonator	12
2.3	Transmission and Reflection phase vs normalized detuning of an asymmetric Fabry-Perot resonator	13
2.4	Phaser plots of complex Transmittivity and Reflectivity of an asymmetric Fabry-Perot resonator	14
2.5	Beer's law plot with attenuation 0.01/cm: y-axis shows the intensity of light and x-axis shows the distance traveled in meters.	16
2.6	Beer's law plot with gain value 0.01/cm: y-axis shows the intensity of light and x-axis shows the distance traveled in meters.	17
2.7	Illustrated fields of an all pass resonator	18
2.8	Reflection and Transmission spectra of a passive All-pass ring resonator	19
2.9	Gain introduced into an all-pass resonator: we see clear difference in the intensities.	19

2.10	Phase diagram of an All-Pass ring resonator from 0 to π where r is the coupling parameter. .	20
2.11	Phaser plots of complex Transmittivity and Re- flectivity of an All-pass ring resonator	20
2.12	Illustrated fields of an add drop resonator	21
2.13	Reflection and Transmission spectra along with their respective phases	22
2.14	Gain introduced into an all-pass resonator: we see clear difference in the intensities.	22
2.15	Phaser plots of complex Transmittivity and Re- flectivity of an All-pass ring resonator	23
2.16	Illustrated fields and geometry of a coupled ring resonator	24

Chapter 1

Introduction

Since the dawn of modern technology, the integrated circuits on which today our every electronic device operates, we have progressed a lot in communication systems and developing faster and smaller computing devices. Decades have passed since electric circuits became integrated on microchips which are also called ICs, this technology has no stop but the field of optical research which generated a great amount of research progress make rise to a new form of technology on which we can operate our computing circuits is called Photonics. Now is the time that we integrate photonic crystals and photonic structures on circuits and make use of them in communication, signal processing, biochemical sensing, slow and fast light structures, optical filters, optical buffers, wavelength division-multiplexed (WDM) and on chip optical interconnects.[1] Every phenomenon mentioned here is made possible by confining light in a very small volume. Microresonators can be used to support spectrum of optical modes with required polarization frequency and field patterns. These research phenomenons will revolution the digital technology as we know today, with every hand-held device to corporate machines, all running on circuits made using photonic crystals and optical microresonators.

On a basic level, there are so far two settled components of light control and direction inside the volume of an optical microresonator. The first is the ordinary system of total internal reflection (TIR) and the presence of evanescent waves, where the directing medium must be optically denser, i.e., have a higher refractive index, than the en-

compassing one so as to accomplish light constrainment. The second is the photonic bandgap (PBG) found in artificial optical media having a spatial periodicity in one, two, or three measurements, named photonic crystals (PC), which is a consequence of the phenomenon of Bragg reflection causing the arrangement of frequency bands where propagation of light is restricted by the destructive interference of field harmonics inside the crystal. Exceptionally bound optical modes can be accomplished in these bands when certain deformities are presented in the generally flawlessly intermittent crystal. With PC defect modes, the light can be bound in a size similar to its wavelength (λ/n), where λ is the vacuum wavelength and n is the medium refractive index.[1]

These topics require a detailed study, which is what we are going to do in this Thesis. The scope of this thesis is not limited to a certain and most applicable type of optical resonator which are known as Whispering Gallery resonators or (WG), but we are also going to extend this research on to different possible and quite promising arrangements and geometries of optical resonators known as Microring resonators. In which we mainly focus on the ring shaped resonators introducing coupling and different modes in single and composite system of resonators. This will allow us to collectively measure and observe the combined effects of such resonators by the help their optical properties and their use in optocommunicating systems. Coupling effects have been observed in detail and have made possible to observed effects like Electromagnetically Induced Transparency and Electromagnetically Induced Absorption in coupled resonator systems which are called Coupled Resonator Induced Transparency and Coupled Resonator Induced Absorption[2].

This documentation is divided into different sections, compiling the work of 1 year long BS final year project. First, we will increase the understanding of the reader of what interferometers, resonators, optical resonators, and microring resonators are, their underlying physics and the phenomenons that are followed by the regimes of these optical systems and what outcome could be acheived by using these optical systems and their applications in photonics. Then we will focus on the

systems that we used in this research process and their basic physical explanations. After that, I will show the results of what I have collected by modeling these systems in different conditions (parameters). This extensive documentation will be useful for anyone trying to get started in this field of research because I have written it in a fashion that a newbie in the field of photonics can easily grasp the ideas and can learn from it.

1.1 Resonators

A resonator is a device that exhibits resonant behavior naturally (or artificially) on some resonant frequencies, that is, it oscillates at those frequencies with higher amplitudes than others. These frequencies are called its resonant frequencies. These oscillations can either be electromagnetic waves or mechanical waves as well. There are different uses of resonators, they can be used to filter some specific frequencies or can also be used to generate a specific frequency of the wave. A resonator in which the waves exist in hollow space is called a cavity resonator, which is used in electronics and radio signal processing, known as microwave cavities, to generate, transmit and receive electromagnetic signals. Acoustic cavity resonators, in which sound is produced by air vibrating in a cavity with one opening, are known as Helmholtz resonators.

1.1.1 Explanation

The term resonator is most often used for a homogeneous object in which vibrations travel as waves, at an approximately constant velocity, bouncing back and forth between the sides of the resonator. The material of the resonator, through which the waves flow, can be viewed as being made of millions of coupled moving parts (such as atoms). Therefore, they can have millions of resonant frequencies, although only a few may be used in practical resonators. The oppositely moving waves interfere with each other, and at its resonant frequencies reinforce each other to create a pattern of standing waves in the resonator. If the distance between the sides is d , the length of a round trip is $2d$. To cause resonance, the phase of a sinusoidal

wave after a round trip must be equal to the initial phase so the waves self-reinforce. The condition for resonance in a resonator is that the round trip distance, $2d$, is equal to an integer number of wavelengths λ of the wave:

$$2d = N\lambda, \quad N \in \{1, 2, 3, \dots\}$$

If the velocity of a wave is c , the frequency is $f = c/\lambda$ so the resonant frequencies are:

$$f = \frac{Nc}{2d} \quad N \in \{1, 2, 3, \dots\}$$

So the resonant frequencies of resonators, called normal modes, are equally spaced multiples (harmonics) of a lowest frequency called the fundamental frequency. The above analysis assumes the medium inside the resonator is homogeneous, so the waves travel at a constant speed, and that the shape of the resonator is rectilinear. If the resonator is inhomogeneous or has a nonrectilinear shape, like a circular drumhead or a cylindrical microwave cavity, the resonant frequencies may not occur at equally spaced multiples of the fundamental frequency. They are then called overtones instead of harmonics. There may be several such series of resonant frequencies in a single resonator, corresponding to different modes of vibration. [3]

1.2 Optical Resonators

An optical resonator, also known as optical cavity, is usually composed of two highly reflecting mirror held in front of each other parallelly inside a vacuum so that the system exhibits resonant behavior which allows standing wave modes to exist with almost no loss. Thus optical resonator is a cavity with walls that are highly reflected for electromagnetic waves (i.e light).




Figure 1.1: Illustration of a basic optical cavity.[4]

1.3 Different Types of Optical Resonators

1.3.1 Fabry-Perot Resonator

A system of two mirrors held parallel to each other and both having high reflectivities shows a resonant behavior at some frequencies of incident light. If both the mirrors have high reflectance, the incident light is still observed to have pass through them without any decrease in the intensity and is detected, which occurs due to phenoemnonas similar to quantum tunneling effects.

1.3.2 Gires-Tournois

It is basically a lossless Fabry-Perot resonator which have a 100% reflecting rear mirror, that means it reflects 100% at all frequencies. Still, some resonant frequencies stays between the mirrors for a longer period of time and thus descript resonant behavior and lead to ultra slow group velocities. This simple device is known for storing spectral power of light which is reflected from it while modifying its phase. That is why it is sometimes referred to as a "phase only" filter.

1.4 Micro Resonators

Microresonators are special type of resonators made from different type of materials which exhibits optical properties while being fabricated on a chip. These kind of resonators are actually useful in observing the effects of optical resonators on a device.

1.4.1 Different Geometries

There are many type of microresonators from which microring-resonators are very useful in making photonic devices and have wide variety of application. Other kind of resonators are also useful for different kind of applications and all have distinct optical properties based on their geometry. (See figure 1.2)




Figure 1.2: Different geometries of microresonators.[3]

1.5 Electromagnetically Induced Transparency and Induced Absorption (EIT and EIA)

Electromagnetically Induced Transparency (EIT), is a coherent optical nonlinearity which makes a medium transparent to some narrow bandwidth of frequencies which were otherwise opaque to the incident radiation. This window leads to slow light at resonant frequencies in an optical resonant system usually involving coupled system. This is observed due to the destructive quantum interference effects of the incident radiation in atomic levels. [5]

Similarly, Electromagnetically Induced Absorption (EIA), is a similar phenomenon to EIT but in this nonlinearity the medium becomes highly opaque to some bandwidth of frequencies at resonance. Thus blocking off completely the resonant frequency radiation and causing a dip in the transmitted field. The quantum interference of light here is destructive and the atomic levels absorb the extra photons at such particular frequencies.

1.6 Aim and Objective

This thesis is a detailed study of such phenomenons dealing optical resonators. We will also deeply study the changing behavior of active and passive resonators. Active resonators are those resonators which are made from some gain medium and they also descript EIT and EIA like behavior in similar and distinct fashion. Then we will model the systems using different scientific tools and computation methods to predict their behavior in different circumstances and parameters.

References

[1] N. Uzunoglu et al., "photonics microresonator research and application," in photonics microresonator research and applicatin, New York, © Springer Science+Business Media, LLC 2010, 2010, p. 515

[2] Induced transparency and absorption in coupled whispering-gallery microresonators, PHYSICAL REVIEW A 71, 043804, published 5 April 2005

[3] <https://en.wikipedia.org/wiki/Resonator>

[4] <https://www.rp-photonics.com/optical-resonators.html>

[5] What is and what is not electromagnetically induced transparency in whispering-gallery microcavities, DOI: 10.1038/ncomms6082, Published 24 Oct 2014

Chapter 2

Fundamental Characteristics of Optical Resonators

2.1 The Fabry-Perot Interferometer

Optical resonators were utilized as helpful gadgets as early as 1899, when Fabry and Perot depicted the utilization of a parallel-plate resonator as a multipass interferometer. Part of the incident light on this Fabry– Perot resonator is transmitted and another part is reflected, with power divisions that rely upon numerous factors. A simple illustration of the basic Fabry-Perot is shown in Figure 2.1, here r_1t_1 are the reflectivity constant and transmittivity constant of the mirror 1 respectively and r_2t_2 are the reflectivity and transmittivity constants of the mirror two respectively. Also, E_i is the incident Electromagnetic energy, E_t is the transmitted energy and E_r is the reflected energy. This is an asymmetric Fabry-Perot resonator:




Figure 2.1: Illustrated energy diagram of a simple Fabry-Perot resonator

2.1.1 Theory of Fabry-Perot interferometer

If the incident energy is in the form of white coherent light then at that point the transmission and reflection coefficients depend just on the mirror reflectivities. The total reflected power comprises of the power reflected from the principal mirror in addition to all the different reflections between the mirrors that add to the reflectivity in general. In summation, the equations are:

$$\mathcal{R} = R_1 + T_1^2 R_2 \sum_{m=1}^{\infty} (R_1 R_2)^{m-1} = \frac{R_1 - 2R_1 R_2 + R_2}{1 - R_1 R_2} \xrightarrow{R_1=R_2 \equiv R} \frac{2R}{1 + R} \quad (2.1)$$

Similarly, the transmitted energy in summation is:

$$\mathcal{T} = T_1 T_2 \sum_{m=1}^{\infty} (R_1 R_2)^{m-1} = \frac{T_1 T_2}{1 - R_1 R_2} \xrightarrow{R_1=R_2 \equiv R} \frac{T^2}{1 - R^2} = \frac{1 - R}{1 + R} \quad (2.2)$$

Assuming, be that as it may, the incident light comprises of a transiently lucid (monochromatic) plane wave, at that point the reflected power will be relative to the square of the reasonable total of every reflected field. Since the fields convey phase information with amplitudes added, the division of reflected and transmitted light depends not just on the mirror reflectivities, but in addition on the mirror separation and excitation wavelength. The rational

total of fields is amplified when every one of the fields interfere constructively (in phase) and limited when they interfere destructively (out of phase).

Phase gathers with propagation separation as $\phi(z) = \beta z$ and may likewise be gained upon communication with the mirrors. The sound forms of

Eqs. 2.1 and 2.2 incorporate an aggregated stage factor for each round-trip that can be translated as a standardized detuning $\phi = T_R \omega$, where T_R is the cavity travel time, $T_R = n_{eff} L / c$ for the circumference, L and effective index n_{eff} . Presently, \tilde{r} speaks to the complex reflectivity:

$$\begin{aligned}\tilde{r} &= r_1 - t_1^2 r_2 \exp(im\phi) \sum_{m=1}^{\infty} (r_1 r_2 \exp(im\phi))^{m-1} \\ &= \frac{r_1 - r_2 \exp(i\phi)}{1 - r_1 r_2 \exp(i\phi)} \xrightarrow{r_1=r_2 \equiv \tilde{r}} \frac{r(1 - \exp(+i\phi))}{1 - r^2 \exp(+i\phi)}\end{aligned}\quad (2.3)$$

and \tilde{t} represents the complex transmittivity:

$$\begin{aligned}\tilde{t} &= -t_1 t_2 \exp(im\phi/2) \sum_{m=1}^{\infty} (r_1 r_2 \exp(im\phi))^{m-1} \\ &= \frac{-t_1 t_2 \exp(im\phi/2)}{1 - r_1 r_2} \xrightarrow{r_1=r_2 \equiv \tilde{r}} \frac{-(1 - r^2) \exp(im\phi/2)}{1 - r^2}\end{aligned}\quad (2.4)$$

The square modulus of these perplexing amounts gives the reflection \mathcal{R} and transmission \mathcal{T} coefficients (shown in Fig. 2.2). Antiresonant wavelengths are more emphatically reflected than in the ambiguous case, while thunderous wavelengths are transmitted 100% for adjusted reflectors ($r_1 = r_2$). For a fixed reflect dispersing, the transmission and reflection spectra in this manner show intermittent pinnacles and valleys. Figure 3.1 presenting the transmission and reflection spectra for a lossless, adjusted Fabry–Perot resonator. The part of reflected and transmitted power for mixed up excitation is identical to the separate frightfully arrived at the midpoint of reflection and transmission over a time of the spectrum range.




Figure 2.2: Transmitted and reflected field of an asymmetric Fabry-Perot resonator

2.1.2 Effective Phase

Now let's look at the phase details of the transmission and the reflection spectra of the asymmetric Fabry-Perot resonator. The phase gives us a lot of details about the travelling light inside the resonator and gives other details about dispersion, group delay and group index. Fig. 2.3 shows phases of both transmission and reflection of an asymmetric Fabry-Perot resonator.




Figure 2.3: Transmission and Reflection phase vs normalized detuning of an asymmetric Fabry-Perot resonator

2.1.3 Phaser plots

Phaser plots are another useful way to study the behavior of light inside the optical cavity. The phaser plots are the complex plots between Real and Imaginary parts of the complex reflectivity and transmittivity (equation 2.3 and 2.4 respectively). Figure 2.4 shows the phaser plots of both transmittivity and reflectivity of an asymmetric Fabry-Perot resonator over the detuning period of 0 to 2π radians.




Figure 2.4: Phaser plots of complex Transmittivity and Reflectivity of an asymmetric Fabry-Perot resonator

2.1.4 Finesse, Q-factor

The resonance condition is fulfilled when the (compelling) circumference of the ring, or for the most part the round-trip length, is equivalent to a whole number numerous of the optical wavelength inside the medium. This means a progression of Lorentzian-molded transmission bends equally dispersed in recurrence by the FSR (Free Spectral Range), with the resonance linewidth portraying the capacity time of photons inside the cavity. The photon lifetime can be standardized to one optical cycle, known as the quality factor (Q), or the cavity round-trip time, known as the cavity Finesse (\mathcal{F}). The most extreme reachable Q -factor is characterized as Q_{int} , which is the intrinsic loss of the cavity. At the point when the resonator is coupled to the outer world, the Q -factor further decreases because of the loss imported by the coupler (Q_{ext}). Thus the last quality factor Q_{load} is comprised of

these two parts: $\mathcal{Q}_{load}^{-1} = \mathcal{Q}_{int}^{-1} + \mathcal{Q}_{ext}^{-1}$.

$$\mathcal{Finesse} = \frac{FSR}{FWHM}$$

$$\mathcal{Finesse} = \frac{2\pi}{2ra \cos\left(\frac{2ra}{1+a^2r^2}\right)}$$

If $ra = 1$ then,

$$\mathcal{Finesse} = \frac{\pi}{1-ra} \quad (2.5)$$

Similarly,

$$\mathcal{Q}_{factor} = \frac{\lambda_{res}}{FWHM}$$

$$\mathcal{Q}_{factor} = \frac{nLf}{\lambda}$$

$$\mathcal{Q}_{factor} = mf \quad (2.6)$$

2.2 Gain incorporation in Resonators

Light, when travels through a medium, loses its intensity exponentially. This law is called the *Beer's law* for electromagnetic intensity. But some mediums, whose refractive index is such as they oppose the exponential decay of the light and rather increase the intensity in the propagation through the medium, are called natural gain medium. Also, there can be artificial source to activate gain in a certain system. This is done by pumping energy or external light source i.e. Lasers, to excite the atoms inside the cavity. This makes the stimulated emission releases of the photons increase exponentially and we see increase in the incident intensity of the input light. We can use these gain

mediums and build microresonators from them and observe different quantum optical phenomenons. First I will explain a bit about how gain works.

2.2.1 Beer's Law

The simple radiation law follows the beer's law in absorption of any kind of radiation inside a medium. This tells us that the initially intensity of the light source depends on the variables of the medium it is passing through. For electromagnetic radiation, we can write this law as,

$$I(z) = I_o \exp^{-\alpha z} \quad (2.7)$$

Here, I_o is the initial intensity of the radiation, α is the attenuation constant of the medium, z is the amount of distance traveled through the medium and $I(z)$ is the intensity of light after traveling the distance z .




Figure 2.5: Beer's law plot with attenuation 0.01/cm: y-axis shows the intensity of light and x-axis shows the distance traveled in meters.

2.2.2 Beer's law study as gain

In a gain medium, the intensity of the light will not decrease but it will gradually increase. This means that the attenuation α is negative or we can introduce a new coefficient for such medium say g such that $-\alpha \rightarrow +g$ where g is some positive real number. This means that

the intensity function now grows exponentially rather than decaying exponentially.

$$I(z) = I_o \exp^{+gz} \quad (2.8)$$




Figure 2.6: Beer's law plot with gain value 0.01/cm: y-axis shows the intensity of light and x-axis shows the distance traveled in meters.

2.2.3 Gain medium

The active laser medium also called gain medium or lasing medium is the source of optical increase inside a laser. The gain is the result of stimulated emission of electronic or sub-atomic changes to a lower energy state from a higher energy state recently populated by a pump source.

2.3 Ring Geometry Resonators

In this section, I will discuss different kinds of ring shaped resonators whose principle is pretty much similar to the Fabry-Perot resonator and are more simple to make. Basically, a ring resonator is a simple waveguide which is turned in the shape of a ring. This allows it to exhibit resonant behavior on very specific frequencies. The light is coupled inside the ring due to the phenomenon of total internal reflection and interference. This kind of behaviour is noticed in all kind of classical waves, such as sound waves, which was observed inside a large cathedral's halls, thus it was named whispering galleries. Also, these

resonators can be made using different material but in this thesis, we used semi-conductor silicon as the primary material.

2.3.1 All-Pass Ringresonator

A straightforward ring resonator is made by taking one yield of a conventional directional coupler and bolstering it once again into one input. Such a device displays periodic cavity resonance (reverberation) when light navigating the ring procures a phase move relating to a number numerous of 2π radians. The resonator is numerically defined from two parts: a coupling quality and an input way. In opposition to the limitless entirety inferences performed before for the Fabry– Perot and Gires– Tournois, in which we expected steadystate task and coordinating fields and derived basic spectral properties. Although, both strategies are similarly substantial, the field-coordinating technique has the benefit of simplicity.




Figure 2.7: Illustrated fields of an all pass resonator

Transmission and Reflection

Let us now look at some reflection and transmission spectra of a passive All-pass ring resonator. Fig. 2.6 shows that the transmission and reflection peaks are flipped as in case of an symmetric Fabry-Perot resonator.




Figure 2.8: Reflection and Transmission spectra of a passive All-pass ring resonator

Transmission and Reflection with gain

Now we introduce gain into the system and observe that the transmission dip also shifts into a peak and goes way above the 1 mark meaning that it is greater than the initial intensity and the reflection peak is also above 1 mark meaning a lot of incident light is being reflected. We will study the transmission of some other different geometries of ring resonators with gain.




Figure 2.9: Gain introduced into an all-pass resonator: we see clear difference in the intensities.

Effective Phase

The phase of the All-pass ring resonator is shown in Figure 2.7. We can easily observe from this that with changing the values of the coupling r , the shape of the graph changes as that of a function of $\text{ArcTan}\phi$.

The relation for phase is given by,

$$\Phi_{eff} = \pi + \phi + 2 \tan^{-1} \frac{r \sin \phi}{1 - r \cos \phi} \quad (2.9)$$




Figure 2.10: Phase diagram of an All-Pass ring resonator from 0 to π where r is the coupling parameter.

Phaser Plots

Now looking into some complex refractivity and transmittivity of an All-pass ringresonator (Fig. 2.7). These plots are plotted over the complex plain from the detuning limits of 0 to 2π . The transmission loop does not go to negative real axis and touches the origin but the reflection curve does not even form a loop.




Figure 2.11: Phaser plots of complex Transmittivity and Reflectivity of an All-pass ring resonator

2.3.2 Add-Drop Ringresonator

The immediate waveguide similarity of a free-space Fabry– Perot is gotten by including a second guide that side-couples to the resonator as in Fig. 1.4. Since this setup acts as a tight band abundance channel that can include or drop a recurrence band from an approaching sign, it is regularly named as an add– drop filter. Fig. 2.8 shows the basic geometry of the add-drop ring resonator with its associated fields labeled accordingly. This resonator has an input, through and drop interfaces where t_1 is add and t_2 is drop coefficients. Input field is labeled as E_1 while the through field is labeled as E_2 . The drop field is on the left top corner labeled as E_5 . The ratio of these fields to the incident/input field defines the total transmittivity and total reflectivity of the filter.




Figure 2.12: Illustrated fields of an add drop resonator

Transmission and Reflection

Let us now look at some reflection and transmission spectra of a passive Add- drop filter. Fig. 2.10 shows that the transmission and reflection peaks are flipped as in case of an asymmetric Fabry-Perot resonator and the transmission phase is a direct function of the detuning. Reflection phase is also shown in Fig. 2.11.




Figure 2.13: Reflection and Transmission spectra along with their respective phases

Transmission and Reflection with gain

Now we introduce gain into the system and observe that the transmission dip also shifts into a peak which is above the 1 mark meaning that it is greater than the initial intensity and the reflection peak is almost near zero meaning most of the incident light is being transmitted. We will study the transmission of some other different geometries of ring resonators with gain.




Figure 2.14: Gain introduced into an all-pass resonator: we see clear difference in the intensities.

Phaser Plots

Now let us see how complex plots of Add drop is different from the All-pass resonator. Fig. 2.11 shows that the loop goes towards the negative real axis as the phase is increased. This tells a lot about the distinct behavior.

Add Drop Ring resonator Imaginary vs Real plots for limits 0 to 2π




Figure 2.15: Phaser plots of complex Transmittivity and Reflectivity of an All-pass ring resonator

2.4 Coupled Ringresonator

Now we turn another optical waveguide into a ring shape and install it on the top of the all-pass ring resonator such that now we have dual ring geometry and a wave guide coupler. This geometry does allow resonant behaviors and the spectra varies largely from an all-pass resonator. In this arrangement, coupling between the two resonators (rings) also play an important role in the spectra of the light that passes through the resonator. Fig. 2.16 displays the basic geometry of the couple ring system we are going to discuss along with their energies.




Figure 2.16: Illustrated fields and geometry of a coupled ring resonator

2.4.1 Evanescent Coupling

This optical system experiences passage of light through both of the rings through evanescent coupling, a classical phenomenon with quantum like properties. This evanescent coupling allow the light propagation through the both rings of the resonator making it a composite of resonant wavelength systems. This is the power transfer of the wave which is dependant on the proximity of the optical resonator and the waveguide also the length or area that has been exposed to the coupler also plays an important role i-e how much part of the waveguide/resonator overlaps. Coupling strength of an ideal coupler is dependant on the interaction length between the two optical modes which means power will transfer more efficiently when the two modes are matched on the basis of their respective phases. This allow us to observe distinct behaviors as well as multiple resonances in transmittance and reflectance.

2.4.2 Coupled resonator induced transparency and induced absorption

Coupled resonators, like the one above, also shows electromagnetically induced absorption and induced transparency known as CRIT and CRIA. These kind of effects are common in atomic systems but we

have observed these effects in a ring resonator system which we will discuss in detail in coming chapters.

References

Chapter 3

Electromagnetically Induced Transparency and Absorption

3.1 EIT in Atoms

Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

3.1.1 Two level Atoms

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

3.2 EIT in ring resonators

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-

precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

3.3 EIT in Coupled resonators(CRIT)

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

3.4 CRIT with gain

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

3.5 Results

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-

precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

3.6 EIA concepts

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some

3.6.1 EIA in atoms

understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are.

3.6.2 EIA Quantum phenomena

This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-

precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are.

3.7 EIA in resonators

This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

3.7.1 Coupled resonators induced Absorption

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

3.8 CRIA with gain

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from nu-

merical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

Chapter 4

Composite Resonator Systems

4.1 Coupled resontaor with Gain medium

Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

4.1.1 Gain element

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

4.2 Calculation/Equations

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from nu-

merical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

4.2.1 For single

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

4.2.2 For coupled

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

4.2.3 For triple

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

4.3 Coupling Regimes

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

4.4 Gain controlled EIT and EIA

Chapter 5

Gain Incorporation

Chapter 6

Conclusion

Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the

possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis. Most of the time, using `mpmath` is simply a matter of setting the desired precision and entering a formula. For verification purposes, a quite (but not always!) reliable technique is to calculate the same thing a second time at a higher precision and verifying that the results agree.

To perform more advanced calculations, it is important to have some understanding of how `mpmath` works internally and what the possible sources of error are. This section gives an overview of arbitrary-precision binary floating-point arithmetic and some concepts from numerical analysis.

Appendix A

Abbreviations

EIT Electromagnetically Induced Transparency

EIA Electromagnetically Induced Absorption

CRIT Coupled Resonator Induced Transparency

CRIA Coupled Resonator Induced Absorption

FSR Free Spectral Range

MRR Micro Ring Resonator

MZI Mach Zehnder Interferometer

FWHM Full width at half maximum

CMT Coupled Mode Theory