

mod_quickjs / builtin functions
(version: 1.0_16012022)

Revisions history:

- 11082021 - initial version
- 16012022 - added glb.functions: *consoleLog*
added glb.objects: *flags*

Table of content:

- [Global functions](#)
- [Global objects](#)

Global functions

- **console_log(level, message)**
• **consoleLog(level, message)**
return: undefined
Logs a message to the console logger.
level - [info | debug | notice | error | warning | critical]
message - any text data
- **include(jsFile)**
return: result of evaluate script file
Includes a file into the current Javascript file.
jsFile - path to the file
- **msleep(tval)**
return: true/false
Make a delay.
tval - time in milliseconds
- **bridge(sessionA, sessionB [, callback, cbArg])**
return: true/false
Bridges 2 channels together (see the Session object).
sessionA - the Session object
sessionB - the Session object
callback - function(session, dtmf, type, cbArg) { ... }
 type - ['dtmf' | 'event']
 cbArg - custom data
- **system(cmd)**
return: int as ret.code
Executes an external system command.
cmd - the command with args
- **exit([retCode])**
return: never returned
Stop the script and generate exception.
- **md5(data)**
return: a hex string
Calculate a MD5 sum for the data.
data - any string data
- **apiExecute(apiCmd, cmdArgs)**
return: hex string
Executes an API (FreeSWITCH console) command.
apiCmd - the command name to execute
cmdArgs - arguments (use space as a separator)
- **setGlobalVariable(name, value)**
return: true/false
Global variables can be used to share information between all channels
name - the name of variable
value - the value as string
- **getGlobalVariable(name)**
return: the variable value or undefined
Global variables can be used to share information between all channels
name - the name of variable

Global objects

flags

Property	Type	Access	Description
odbcEnabled	string	R0	true if module was compiled with ODBC support
curlEnabled	string	R0	true if module was compiled with CURL support