

Buttons

Design guideline

Code view

Sizes

We have two sizes of buttons, default and small. The default button size is 42px. The small button is 35px height and is used when creating a complex form with space constrictions.

Primary

Default

Primary

42px

Text: 18px #FFFFFF

Secondary

Secondary

42px

Text: 18px #333333

Tertiary

Tertiary

35px

Text: 16px #333333

Button with icon

+ Add

42px

Text: 18px #333333

Button in a field

Search

Q

42px

Icon is centered on button vertically & horizontally

Small

Primary

35px

Text: 16px #FFFFFF

Secondary

Secondary

35px

Text: 16px #333333

No small size for tertiary button

+ Add

35px

Text: 16px #333333

Search

Q

35px

States Fill & Stroke Specifications

Primary

Primary

Secondary

Tertiary

Button with icon

Button in a field

Normal

Primary

Primary

Secondary

Tertiary

+ Add

Search

Q

Hover/tap

Primary

Primary

Secondary

Tertiary

+ Add

Search

Q

Disabled 40% opacity

Primary

Primary

Secondary

Tertiary

+ Add

Search

Q

Use browser focus state

Primary

Primary

Secondary

Tertiary

+ Add

Search

Q

Default

Primary button

Primary

If no financial institution color is available the primary button is - HEX#666666

Button Interaction Details

Primary vs. Secondary Buttons

Primary - use for the primary action that the user must take on the page.

Primary and secondary - use both when there is a choice between two actions and we can recommend one action over the other and/or the secondary button is used to cancel out of the action.

If multiple actions have equal value then use all primary buttons.

Tertiary Buttons used when not the main action on the page.

Large vs. Small Buttons

Use the Large button sizes almost exclusively in designs. Exceptions are when there is not enough room on the page for the 42px height (example: inside a table)

If there are multiple choices for non-primary actions on the page then use the tertiary button for of those actions. See examples below.

*Critical tasks should not depend on disabled buttons in order to understand the action.

Other Types of Buttons

Input with dropdown

Search

52px

42px

Search

42px

35px

See drop down section of guide to find interaction detail on the input with dropdown button (follows the same details as other drop downstyles)

Toggle buttons

ON

OFF

The Toggle Button is divided into two segments and behaves as a single-selection control, allowing the user to click and immediately initiate an action.

The toggle state allows you to highlight the current state. Ex.: Yes/No, On/Off. It should use the FI primary accent color or the default color of #666666 in the on state.

Links as buttons

[Link](#) Default color is [#0055CC](#), should use FI link color

A link is used to take action or initiate an action.

They should be used when there are multiple actions to be taken on the page and using a push button would make the page visually heavy.

- Links are underlined or have an icon near them to indicate it is a tappable area for accessibility. • When the link is selected (hover, focus, or active) the underline disappears.
- They should follow the branding color for links - FI Primary accent color (default color #0055CC). • The minimum font size for links is .875 em and the maximum is 1.125 em.
- They can sometimes contain icons to the right of the link, but icons are not mandatory.
- The rules for labeling apply to link buttons as well (shown later).
- For Link buttons to be tablet-friendly, the padding around the link should be big enough for a user to select by touch. Height for the target area should be 42px.

Stand alone link

[Link](#)

The padding around the stand alone link (when not as a part of other Link non-link text) should be large enough for user to select by touch without tapping something else accidentally: 20 px min each side to next tappable area.

Link with icon

Sample text

Sample text

Example of link with icon using #333333

Example of link with icon using link color

Icons as buttons

- An icon alone works best when the action can be represented by a symbol that's well understood. An alt value is required.
- If there is any doubt to an icon's meaning, use a word next to it to clarify.
- An icon may have a hover state but it is not mandatory.
- One common example of an icon used as a button is the close icon on overlays.
- Another example is the help icon.

Other Button Details

Spacing between buttons:

Make transfer

10px

Cancel

The space between buttons is always equal to 10 px, regardless of the button type and size.

Button width:

S, M, L

Save

20px

Cancel

20px

The width of the button is a minimum of 20 px from the centered text to each edge.

XS

Save

10px

Cancel

At the XS breakpoint the buttons are 100% width.

Processing

For processes that take several seconds, disable the submit button until the process is complete and the user receives confirmation feedback.

Examples

How to use buttons on an overlay

They are left-aligned to the bottom left corner of the overlay.

Overlays also use the close icon button placed in the top right corner. This usually closes the overlay without any confirmation.

For accessibility: when an overlay opens, default focus is on the close button. Tab order moves from close to the overlay content to the primary button and then to the secondary button. Recommended practice: source order determines the path, as opposed to changing tab index of elements.

Please confirm

Transfer

This is the amount due to pay down the loan. Your account will be closed.

From

Checking *7676

To

Savings *7777

Amount

\$100.00

?

Lorem ipsum dolor (DI text same as today).

FI configurable text - ipsum dolor sit amet, consectetur adipiscing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam.

Confirm

Cancel

Secondary Button
Used for a secondary action or to cancel out of an action.

Primary Button (default is HEX#767676 to HEX#666666 but should use FI Button color)
Used for the main action user needs to take on the page.

My settings

Overview

Update password

Personal settings

Update contact information

Update email options

Login & Security settings

Update username

Update password

Update security options

Other settings

Rename & Hide accounts

Alerts & Notifications

Current password

New password

Retype password

Minimum of six characters
Use a mix of letters, numbers or symbols
Passwords must match

Save

Cancel

Primary Button:
default is HEX#767676 to HEX#666666 should use FI Button color

Secondary Button

Have a question? [Check our FAQs](#) | We value your opinion. [Make a suggestion](#)

Banking on Panther. All Rights Reserved

Protecting your privacy is our top priority. Please refer to our [privacy policy](#).

NCUA

Your deposits are federally insured by up to \$250,000 and backed by the full faith and credit of the United States Government.

National Credit Union Administration, a U.S. Government Agency

CDL

Tertiary Button
Used when not the main action on the page.

Multiple tertiary buttons

Personal Checking

Change

Available \$1861.70

Account Details

Current \$2,508.72

Make a Transfer

Online Statements

Print

Export

Dec 28, 2015 - Jan 26, 2016

30 days

Narrow by items containing: e.g. AT&T, check

Date

Description

Deposits

Withdrawals

Balance

Pending

TJ MAXXX #367 00000084847474733020

-\$68.45

\$1861.70

Dec 15, 2015

ABC COMPANY PAYROLL DEPOSIT

+\$1,523.25

\$1930.15

Please confirm

Transfer

This transfer will incur a fee of \$4.50.

From

ADVANTAGE 50 CHECKING 0009

To

Business Checking NEW 1315

Amount

\$10.00

?

Once this transfer is made, it cannot be cancelled.

DI9907:The transfer confirmation and transfer success messages from Financial Institution for verification the new implementation.

Confirm

Cancel