


Free Energy is the Energy Available for Work

Free Energy is the Cell's Available Energy


Free Energy is energy [available to do work](#).

- It can be considered the analog of potential energy in a "thermal environment" (where molecular collisions substantially alter the potential and / or kinetic energies of objects of interest - i.e., proteins, solvent, etc.).
- Systems will move from a condition of high to low free energy if it is possible: a ball will roll downhill in the absence of a barrier.
- The cell stores free energy in two primary ways:
 - (1) a gradient - i.e., [differing concentrations of ions or small molecules across a membrane](#), as is the case for some [transporters](#).
 - (2) [activated carriers](#) - i.e., molecules capable of dissociating, but which are maintained at a concentration well above the equilibrium value, such as [ATP](#) and GTP.
- Any system that is out of [equilibrium](#) stores free energy that can be used for work - e.g., to drive cellular processes such as transport, locomotion, [synthesis](#) - or signaling processes. Conversely *an equilibrium system stores no free / usable energy* unless the conditions are changed.

Activated Carriers Store Free Energy



Activated,
non-equil. state:



Equilibrium:

$$[\text{GTP}] k_{off} = [\text{GDP}] [\text{P}_i] k_{on}$$

$$[\text{GTP}] k_{off} > [\text{GDP}] [\text{P}_i] k_{on}$$

Catalyzing the rxn
will cause "flow": GTP
hydrolysis to GDP + P_i .
Free energy is available.


Catalyzing the rxn
will do nothing -
No free energy is stored.

(*) If net flow can
occur, free energy
is stored.

The cell maintains the concentration of an activated carrier (e.g., GTP or ATP) well above its equilibrium value so that there is always a driving force toward equilibrium (via the decomposition reaction). Because there is a drive toward equilibrium, there is free energy which can be harnessed for work - as in the example of [ATP-driven transporters](#).

Concentration Gradients across Membranes Store Free Energy

Example: Na^+ concentrations across a membrane



Non-eg: $[\text{Na}^+]_{\text{out}} \neq [\text{Na}^+]_{\text{in}}$

Free energy is available.

Equil: $[\text{Na}^+]_{\text{out}} = [\text{Na}^+]_{\text{in}}$

No free energy is stored.

As in the case of activated carriers, gradients are also out of equilibrium: there is a driving force to equalize the concentrations of species across a membrane (assuming for simplicity no coupling among species). A [more quantitative discussion of this phenomenon](#) is available. The cell can use gradient-stored free energy, for instance in the case of active [transport](#).

The Cell Uses Free Energy in Different Ways

In general, the cell uses free energy it stores in gradients and activated carriers to accomplish two types of things:

- (1) [Work](#) in the usual sense - i.e., energetically unfavorable tasks such as transport (against a gradient), locomotion, and chemical synthesis.
- (2) Energy-neutral signaling processes, such as phosphorylation, which involve a specific sequence of events that may leave the signal carriers (e.g., proteins) unchanged.


How does the free energy remain stored without "running downhill"?

Free energy in the cell will not dissipate unless the transition from the high-free-energy non-equilibrium state toward a lower free-energy state is [catalyzed](#): for [activated carriers](#), enzymes are required; for gradients across membranes, flow is enabled by channels or [transporters](#).

How does the cell get energy?

The cell maintains its supply of ATP and other stored energy by metabolizing nutrients in an ongoing cycle of ATP synthesis.

Cycles and the Cell's Non-equilibrium Use of Free Energy



Cellular processes typically function in cycles to re-use molecular components, and free energy is used to drive such cycles in a single direction by maintaining some components out of equilibrium - e.g., supplying excess ATP or other substrates for catalysis.

Phosphorylation Cycle

Free energy is used to synthesize excess ATP, which drives the cycle 