

A Quick Guide to DipoleCalc

Francis Pratt (francis.pratt@stfc.ac.uk)


1. Introduction
2. Saving and Loading Structures
3. Defining Unit Cell Parameters
4. Spin Sublattices
5. Symmetry Generators
6. Cutoff, Sampling and Demagnetization
7. Test Points and the Site List
8. 2D Scan of a Defined Plane
9. 3D Scan of the Full Cell
10. SDW Modulated Spin Systems
11. Spin at the origin
12. Output Files
13. Examples

1. Introduction

DipoleCalc is an interactive Windows program developed by Francis Pratt as a tool to enable one to explore and assess dipolar fields at potential muon sites for magnetically ordered crystalline materials.


2. Saving and Loading Structures

Structures and calculation parameters can be saved and loaded again with the save and load buttons in the 'Structure' box. The text box allows a description to be included along with the structure. Structure files have the extension .str and are stored in a simple readable and editable text format.



3. Defining Unit Cell Parameters

The unit cell parameters in degrees and Ångstrom are defined in the 'Cell' box. For orthorhombic cells the 'simple' option is selected. For most other cells the 'other' option must be used. For simple FM systems the 'FC' (face-centred) or 'BC' (body-centred) options can be used. The Cartesian definition of the lattice vectors or reciprocal lattice vectors is displayed on the right.



4. Spin Sublattices

The ordered magnetic sublattices can be defined in the first tab on the top right of the window labelled 'Electronic Spin Lattice'. The position within the cell, the moment and the spin direction are defined for each sublattice. Up to 20 sublattices may be specified in this way. The example shows two sublattices defined for a simple body-centred AFM structure, with the remainder flagged as not being used by having zero moment. Sublattices can be given descriptive names by clicking the sublattice box titles.

Electronic Spin Lattice	Field Map	Contour Map	2D Site List	Field Distribution	G(t)	Symr
Sublattice 1						
Origin	0 0 0					
Moment gS	1					
Spin Dir	0 0 1					
Sublattice 2						
Origin	0.5 0.5 0.5					
Moment gS	-1					
Spin Dir	0 0 1					
Sublattice 5						
Origin	0 0 0					
Moment gS	0					
Spin Dir	0 1 0					
Sublattice 6						
Origin	0 0 0					
Moment gS	0					
Spin Dir	0 1 0					
Sublattice 9						
Origin	0 0 0					
Moment gS	0					
Spin Dir	0 1 0					
Sublattice 10						
Origin	0 0 0					
Moment gS	0					
Spin Dir	0 1 0					

5. Symmetry Generators

An additional way of defining magnetic sublattices is via the 'Symmetry Generators' tab page. This provides a list of symmetry operations that are to be applied to each sublattice defined in the 'Electronic Spin Lattice' page. The total number of spin elements is thus the product of the number of elements in these two pages. The examples below shows an alternative way of defining the BCC-AFM using a single sublattice and two symmetry generators. Superlattice periods can also be defined within the symmetry generators page.

Electronic Spin Lattice	Field Map	Contour Map	2D Site List	Field Distribution	G(t)	Symr
Sublattice 1						
Origin	0 0 0					
Moment gS	1					
Sublattice 2						
Origin	0 0 0					
Moment gS	0					
Sublattice 5						
Origin	0 0 0					
Moment gS	0					
Sublattice 6						
Origin	0 0 0					
Moment gS	0					
Sublattice 9						
Origin	0 0 0					
Moment gS	0					
Sublattice 10						
Origin	0 0 0					
Moment gS	0					

Electronic Spin Lattice	Field Map	Contour Map	2D Site List	Field Distribution	G(t)	Symmetry Generators	Site List
Name	Inversion/reflection/rotation	Displacement	Spin sign	Origin unit	Spin Direction		
A	1	1	1	0.00	0.00	0.00	1
A	1	1	1	0.00	0.00	0.00	1
B	1	1	1	0.50	0.50	0.50	-1

Superlattice periods
 a:
 b:
 c:

6. Cutoff, sampling and demagnetization

The 'Sampling and Demagnetization' box defines the cutoff radius for the dipolar sum, the grid resolution used for 2D and 3D scans and the demagnetization factor that applies in the case of a ferromagnet.

7. Test Points and the Site List

The 'Examine Test Point' box is used to test the dipolar field vector and precession frequency at individual sites within the magnetic structure. A set of site positions can be maintained via the 'Site List' tab and used as test points.

Examine Test Point

Position:
 Abs:

☒ cell
☐ abs

Lorentz Field = (0.0 0.0 0.0) 0.0 G
 Demag Field = (0.0 0.0 0.0) 0.0 G
 Lor+Demag = (0.0 0.0 0.0) 0.0 G

Dipole Field = (34.8 34.8 -74.1) 88.9 G
 Total Field = (34.8 34.8 -74.1) 88.9 G (1.21 MHz)
 Orientation = (67.0 67.0 146.4) degrees

Dipole energy =

Electronic Spin Lattice	Field Map	Contour Map	2D Site List	Field Distribution	G(t)	Symmetry Generators	Site List
Name:	<input type="text" value="Site1"/>	Coordinates:	<input type="text" value="0.000 0.000 0.000"/>	<input type="button" value="Use as Test Point"/>			
							<input type="button" value="Add"/> <input type="button" value="Delete"/> <input type="button" value="Update"/>
Name	x-fraction	y-fraction	z-fraction				
H7A	0.9519	-0.1416	0.2810				
H7B	0.9620	-0.1719	0.4395				
H8A	0.7776	-0.1842	0.4304				
H8B	0.8402	-0.2066	0.2839				
H9A	0.3931	0.2108	0.3358				
H9B	0.4581	0.1835	0.2029				
H10A	0.2730	0.1723	0.1888				
H10B	0.2788	0.1466	0.3578				

8. 2D Scan of a Defined Plane

If it is desired to map the dipolar field within the lattice then options to scan over a 2D plane and over the full 3D lattice are offered. The '2D Scan of Defined Plane' box is used to make a 2D scan. An origin and scan vectors must be defined before making the scan. After the scan is complete the data may be viewed via three alternative tab pages 'Field Map', 'Contour Plot' and 'Field Distribution'. The range and binning for the field distribution plot are specified in the 'Parameters for Field Histogram' box. Broadening can be applied to the field distribution to smooth out the sampling noise.

2D Scan of Defined Plane

Origin:

X vector:

X min (Å):
X max (Å):


Y vector:

Y min (Å):
Y max (Å):

Origin/Vector Coords
☐ cell
☒ abs


2D SCAN

Electronic Spin Lattice Field Map Contour Map 2D Site List Field Distribution



Map B min: Grid min = 50.0996
Map B max: Grid max = 2332.77

Electronic Spin Lattice Field Map Contour Map 2D Site List Field Distribution G(t)



Contour level: G ☐ Show Points

Parameters for Field Histogram

B min (G):
B range from scan
Bmin=50.0996

B max (G):
Bmax=2332.77

B bin (G):
B cutoff (G):


☐ Atom exclusion list
☒ Use smoothing

Field Component for Plot
☒ ZF poly (modulus)
☐ TF poly (weighted lineshape)
☐ TF crystal (field projection)

B vector:

☐ ZF crystal (FB projected weight)

Electronic Spin Lattice Field Map Contour Map 2D Site List Field Distribution G(t) Symmetry Generators Site List




Calculate, show and save plot

☐ Overlay
☒ Field distribution
☐ Broadened field distribution
☐ Bayesian moment PDF

Save as: Broadering: G

9. 3D Scan of the Full Cell

To map the dipolar field within the entire magnetic cell the '3D Scan of Full Unit Cell' box is used. If a multicore processor is available then there is an option to speed up the calculation with parallel processing. After the calculation is complete, there is an option to view the cell averaged field distribution or alternatively view the results as a series of planes with different z-values. The grid array of local field vectors can be saved and reloaded later.



3D Scan of Full Unit Cell

3D scan options

- ☒ Use parallel cores
- ☐ Random sign of spin

Cell points=9261

3D SCAN

Grid Array of Local Fields



- ☒ Cell average

z-plane 1

cell:0.000 abs: 0.000

Save

Load



10. SDW Modulated Spin Systems

The field distribution at the test point from an incommensurate periodic modulation of the moments by a spin density wave can be simulated using the 'Field Distribution from Incommensurate SDW' box. The q vector of the modulation is defined and the direction and amplitude of modulation is defined either by a single modulation vector for the case of a linear SDW or by a pair of modulation vectors acting in quadrature for the case of a helical SDW. The modulation can be chosen to either add to the existing moments or replace them. A modulated contact hyperfine term acting in addition to the dipolar fields can also be specified in units of Gauss per Bohr magneton.

Electronic Spin Lattice Field Map Contour Map 2D Site List Field Distribution G(t) Symmetry Generators Site List

Name: Coordinates:

Name	x-fraction	y-fraction	z-fraction
Site I	0.5320	0.5320	0.5320
Site II	-0.0320	-0.5320	0.0320
Site III	0.0320	-0.0320	-0.5320
Site IV	-0.5320	0.0320	-0.0320
Site Ib	0.7210	0.7210	0.7210
Site IIb	-0.2210	-0.7210	0.2210
Site IIIb	0.2210	-0.2210	-0.7210
Site IVb	-0.7210	0.2210	-0.2210

Field Distribution from Incommensurate SDW

q vector (cell)

Mod vec1 (cell) Amp1

Mod vec2 (cell) Amp2

Sample points HF(G/ μ_B)

☐ Add moment
☒ Replace moment

11. Spin at the origin

It is sometimes useful to be able to switch off the spin at the origin of Sublattice-1. One reason is to calculate the dipolar stabilisation energy of a spin structure. After turning off the spin, taking a test point at the origin will calculate the dipolar field seen at the origin and the corresponding dipolar stabilisation energy. Another reason for switching off the spin is to account for molecular singlet formation when a muonium spin pairs up with a molecular radical spin. To allow for the spin being delocalised over one or more molecules, the Symmetry Generators page enables the assignment of whole sublattice groups (e.g. molecules) to the 'Origin unit'. These groups of sites then all switch off together when 'No spin' is selected.

Spin at Origin of Sublattice-1 (select no spin for dipolar energy)

☒ Single spin
 ☐ Double spin
 ☐ No spin

Electronic Spin Lattice	Field Map	Contour Map	2D Site List	Field Distribution	G(t)	Symmetry Generators	Site L		
Name	Inversion/reflection/rotation			Displacement			Spin sign	Origin unit	Spin Direction
A1a	1	1	1	0.00	0.00	0.00	1	Yes	0 0 1
A1a	1	1	1	0.00	0.00	0.00	1	Yes	0 0 1
A1b	-1	-1	-1	0.00	0.00	0.00	1	Yes	0 0 1
A2a	-1	1	1	0.50	0.00	0.50	-1	No	0 0 1
A2b	1	-1	-1	0.50	0.00	0.50	-1	No	0 0 1

12. Output Files

A number of files are automatically saved in the working directory. Bdist.dat is the unbroadened field distribution, Bdistb.dat is the broadened field distribution and timedomain.dat is the relaxation function for the case of stopping at all points in the distribution. The field distribution may also be saved as a named file using the 'Save as' button.

13. Examples

A few example structures are included, starting with a simple cubic ferromagnetic structure stored in folder 'cubic FM'.

A second example is a body-centred-cubic antiferromagnetic structure in folder 'BCC-AFM'. Two ways of defining the same structure are illustrated: 'BCC-AFM-sublattice.str' uses two sublattices and 'BCC-AFM-symmetry.str' uses one sublattice and two symmetry generators.

A more complicated example is given in folder 'Molecular AFM' where the sublattice page is used to define a spin density that is delocalised across a molecule and the symmetry generators page is used to define the eight molecules in the magnetic cell. The site list page is used to define proton sites for estimating the proton NMR spectrum.

The final example is MnSi which is an incommensurate SDW system with a helical spin modulation. Both left-handed and right-handed structures are included, only one helicity is found to be consistent with muon experiments.