

Thermodynamics

Giuliano Maurizio Laudone

Lecture 1

Review of year 1 Thermodynamics

- Thermodynamics developed in the 19th century from the studies on steam engines, focusing on the transformation of *heat* into *work* and vice versa.
- It's entirely empirical. There is no direct proof of the laws of thermodynamics. They are postulated on the basis of experimental evidence.
- It's universal.

A few definitions

System: the part of the Universe that we choose to study. The correct choice of system is often the most critical step in solving a thermodynamics problem correctly.

Surroundings: the rest of the Universe.

Boundary: what separates the system from the surroundings.

An *open* system can exchange mass and energy with its surroundings. A *closed* system can exchange energy but not mass with its surroundings. An *isolated* system cannot exchange mass nor energy with its surroundings.

The complete description of the state of a system requires the knowledge of such variables as:

- p : the pressure of the system
- T : temperature
- V : the volume of the system
- m : the mass of the system
- n_i^α : the composition of each phase of the system

Properties of a system can be *extensive*, when their value is dependent on the size of the system (such as V , n , m) or *intensive*, when their value does not depend on the size of the system (such as T and p). The molar version of an extensive property, for example the molar volume $\bar{V}_i = \frac{V}{n_i}$, is an intensive property.

The way a system evolves in time from one state to another or the speed of such transformation are not described by thermodynamics. For example, thermodynamics can tell us if any two chemical species will spontaneously react to form a third species, but it will not give us any indication on the time needed for such chemical reaction to happen.

Thermodynamics focuses in particular on *states of equilibrium*, states that do not vary if the external conditions do not change. A transformation can be:

- Reversible when all the successive states are infinitesimally close to a state of equilibrium.

- Irreversible.
- Adiabatic when there is no heat transfer between system and surroundings.
- Isobaric: constant pressure.
- Isothermal: constant temperature.
- Isometric or isochoric: constant volume.

A thermodynamical property of a system is a *state function* if its value is a function only of the current state of the system, being completely independent of the previous states of the systems and of the transformations the system underwent to reach its current state. A *path function* is a property dependent from the path of the system transformation. If a property Z of a system is a function of state, and the system changes from an initial state (i) to a final state (f), then the overall change in the value of Z is given only by the difference of its final and initial value:

$$\Delta Z = \int_i^f dZ = Z_f - Z_i$$

This means that the differential of a state function is *exact*, while that of a path function is *inexact* and their integral must be evaluated along the path that describes the changes of the system. State functions are usually identified with upper case letters. The change of a state function on a close path (where the initial and final states are identical) is 0:

$$\oint dZ = 0$$

Work and heat

Work

There are many forms of work, such as electrical, mechanical and gravitational work. In the study of thermodynamics we will mostly focus on a particular type of mechanical work, *expansion work*:

$$dw = -p_{\text{ext}} dV$$

The minus sign is due to the convention that work done by the system is negative, while work done by the surroundings onto the system is positive. Work is not a state function and its total value during a transformation is a function of the path of the transformation.

Heat

Heat is the transfer of energy that results in a temperature change of the system and/or the surroundings. Heat, just as work, is a path function. By convention, its sign is positive if heat enters the system and negative if it leaves the system.

The laws of thermodynamics

Zeroth law of thermodynamics: Two systems that are both in thermal equilibrium with a third system are in thermal equilibrium with each other. This seems just common sense, but the definition of the zeroth law is what the concept of temperature and its measurement are based upon.

Joule designed a clever experiment which demonstrated that it is possible to increase the temperature of a system just by applying mechanical work to it. By doing so, he demonstrated the equivalence of work and heat.

Experimentally it was found that:

$$\oint dq + dw = 0$$

This implies that there is a state function, which we call *internal energy* U with differential

$$dU = dq + dw$$

This is the mathematical formulation of the **first law of thermodynamics**. For a system change between two states the values of work and heat are dependent from the path of the transformation, but their sum is not.

For a reversible process at constant volume ($dV = 0$) the gradient of the internal energy with temperature is the heat capacity at constant volume. C_V is an extensive property.

$$\left(\frac{\partial U}{\partial T}\right)_V = C_V$$

The **second law of thermodynamics** puts limits on the conversion of q to w . It could be formulated using the Kelvin postulate: it is impossible for any system to operate in a cycle that takes heat from a hot reservoir and converts it to work in the surroundings without at the same time transferring some heat to a colder reservoir. An alternative formulation is: all spontaneous processes are irreversible. The mathematical formulation of the second law of thermodynamics is:

$$\oint \frac{dq_{\text{rev}}}{T} = 0 \quad \text{and} \quad \oint \frac{dq_{\text{irrev}}}{T} < 0$$

The state function whose differential is $\frac{dq_{\text{rev}}}{T}$ is called **entropy** S .

Third law of thermodynamics: the entropy of a pure, perfectly crystalline substance is zero at the $T = 0$ K. A consequence of the third law is that it's impossible to decrease the temperature of a system to 0 K in a finite number of steps.

Enthalpy and chemical reactions

Enthalpy is defined as:

$$H = U + pV$$

For a reversible process at constant pressure ($dp = 0$) the gradient of enthalpy with temperature is the heat capacity at constant pressure.

$$\left(\frac{\partial H}{\partial T}\right)_p = C_p$$

C_p is an extensive property. For an ideal gas:

$$\bar{C}_p - \bar{C}_V = R$$

where \bar{C}_p and \bar{C}_V are the molar heat capacities.

Hess's law: the total enthalpy change of a chemical reaction is independent of the sequence of steps the reaction may be divided into. As a consequence:

$$\Delta H_{r,i}^\ominus = \sum_i \nu_i \Delta H_{f,i}^\ominus$$

where $\Delta H_{r,i}^\ominus$ is the standard reaction enthalpy, $\Delta H_{f,i}^\ominus$ is the standard enthalpy of formation for each component i , and ν_i is the stoichiometric coefficient of component i (positive if i is a product of the reaction and negative if it's a reactant).

Kirchhoff's law


We have this set of transformations:

A - R reacts at T_1 to form P ,

B - the temperature of R changes from T_1 to T_2 ,

C - R reacts at T_2 to form P ,

D - the temperature of P changes from T_2 to T_1 .



H is a state function, so the variation of enthalpy is only a function of the initial and final state and it's not a function of the path. In this case path **A** and path **B+C+D** have the same initial and final state, which means that the overall change in enthalpy must be the same. The change in enthalpy for steps **A** and **C** is simply the reaction enthalpy at T_1 and T_2 respectively.

How can we calculate the change of enthalpy for stages **B** and **D**? We know that the variation of enthalpy with temperature can be expressed as $\left(\frac{\partial H}{\partial T}\right)_p = C_p$. By integrating with the correct limits we obtain:

$$\Delta H_B^\ominus = \int_{T_1}^{T_2} C_{p,R}^\ominus dT \quad \text{and} \quad \Delta H_D^\ominus = \int_{T_2}^{T_1} C_{p,P}^\ominus dT = - \int_{T_1}^{T_2} C_{p,P}^\ominus dT$$

We can write $\Delta H_A = \Delta H_B + \Delta H_C + \Delta H_D$ in the form:

$$\Delta H_{r,T_1}^\ominus = \int_{T_1}^{T_2} C_{p,R}^\ominus dT + \Delta H_{r,T_2}^\ominus - \int_{T_1}^{T_2} C_{p,P}^\ominus dT$$

Solving for $\Delta H_{r,T_2}^\ominus$

$$\Delta H_{r,T_2}^\ominus = \Delta H_{r,T_1}^\ominus + \int_{T_1}^{T_2} C_{p,P}^\ominus dT - \int_{T_1}^{T_2} C_{p,R}^\ominus dT = \Delta H_{r,T_1}^\ominus + \int_{T_1}^{T_2} (C_{p,P}^\ominus - C_{p,R}^\ominus) dT$$

Setting $(C_{p,P}^\ominus - C_{p,R}^\ominus) = \Delta C_p^\ominus$ we finally obtain:

$$\Delta H_{r,T_2}^\ominus = \Delta H_{r,T_1}^\ominus + \int_{T_1}^{T_2} \Delta C_p^\ominus dT$$

which is the mathematical formulation of Kirchhoff's law. It means that the reaction enthalpy at temperature T_2 can be calculated if the reaction enthalpy at temperature T_1 and the heat capacities of all the chemical species involved in the reaction are known.

An alternative derivation of Kirchhoff's law.

The enthalpy change of a chemical reaction under standard conditions is:

$$\Delta H_r^\ominus = H_{\text{products}}^\ominus - H_{\text{reactants}}^\ominus$$

By differentiating this expression with respect to temperature we obtain:

$$\frac{d\Delta H_r^\ominus}{dT} = \frac{dH_{\text{products}}^\ominus}{dT} - \frac{dH_{\text{reactants}}^\ominus}{dT}$$

therefore:

$$\frac{d\Delta H_r^\ominus}{dT} = C_{p,\text{products}}^\ominus - C_{p,\text{reactants}}^\ominus = \Delta C_p^\ominus$$

Integrating this between T_1 and T_2 results in:

$$\Delta H_{r,T_2}^\ominus = \Delta H_{r,T_1}^\ominus + \int_{T_1}^{T_2} \Delta C_p^\ominus dT$$

The value of ΔC_p^\ominus can be calculated with:

$$\Delta C_p^\ominus = \sum_i \nu_i \bar{C}_{p,i}^\ominus$$

where ν_i is the stoichiometric coefficient of component i (positive if i is a product of the reaction and negative if it's a reactant) and $\bar{C}_{p,i}^\ominus$ is the molar heat capacity at constant pressure of species i . On small temperature ranges the heat capacity of substances can be considered independent of temperature. However, on larger temperature intervals such approximation is not acceptable. The dependency of heat capacity from temperature can be expressed in the form:

$$C_p = a + bT + \frac{c}{T^2} + \dots$$

or:

$$C_p = a + bT + cT^2 + \dots$$