

# **Site Service Installation Guide**

LS One – 2017



# Contents

<b>1</b>	<b>Introduction.....</b>	<b>3</b>
1.1	The Purpose of This Document.....	3
1.2	Functional Overview .....	3
1.3	Demonstration Data .....	3
1.4	Icons Used in this Guide.....	3
<b>2</b>	<b>Installation .....</b>	<b>4</b>
2.1	Installing LS One Site Service.....	4
<b>3</b>	<b>Configuration.....</b>	<b>5</b>
3.1	Using LS One Site Manager .....	5
3.2	Manual configuration.....	7
3.3	Common Alterations: .....	8
<b>4</b>	<b>LS One Site Service - Features.....</b>	<b>8</b>
<b>5</b>	<b>Connecting the LS One POS.....</b>	<b>8</b>

# 1 Introduction

## 1.1 The purpose of this document

The purpose of this document is to give a quick overview of LS One Site Service. The topics include installing the application, proper configuration, features and client (LS One POS) connections.

## 1.2 Functional overview

LS One Site Service gives LS One POS access to centralized data in real time, such as hospitality table statuses, centralized transaction suspension and centralized staff management. It also provides centralized gift card handling, and centralized loyalty point handling.

## 1.3 Demonstration data

The Demonstration Data is based on a fictitious company, Aurora International Ltd. This company is located in France and its company currency is the Euro. All the data in this company is fictitious and not necessarily correct in all countries.

## 1.4 Icons used in this guide



Tip



Note



Warning

## 2 Installation


### 2.1 Installing LS One Site Service



LS One Site Service should be installed on the “Head office” level of the store where the Site Manager resides.

Run **LSOneSiteServiceInstall.exe** from the LS One Site Service setup package and accept all default choices suggested by the install wizard. When the installation is complete, please verify the installation by confirming that LS One Site Service has started in the list of available services on the computer. To verify this, please access the computer management and locate LS One Site Service in the list of started services.


#### 2.1.1 Image: Services view




## 3 Configuration

To configure the LS One Site Service you need to either use the LS One Site Manager to configure the LS One Site Service, or manually edit the “*LS One Site Service.config*” configuration file.


### 3.1 Using LS One Site Manager

Under Store Setup -> Profiles -> Site service profiles, you can click on the  button to add a new Site Service profile.




A dialog box titled "New site service profile" with a question mark icon in the top right corner. The main text says "Enter profile description for the new transaction service profile". Below this, there is a text input field labeled "Description:" containing the text "LS One Site Service". Below the input field is a dropdown menu labeled "Copy from:" with the selected option "Do not copy existing profile". At the bottom right, there are two buttons: "OK" and "Cancel".

Once you click OK, you will be presented with the next screen where you can set up the connection. In the dialog below, the site service is set up on a local computer, but you can use an IP address or a configured machine name instead. The default port is 9101.




A dialog box with two tabs: "Connection" (selected) and "Settings". The "Connection settings" section contains two text input fields: "Site service host:" with the value "localhost" and "Site service port:" with the value "9101". To the right of the port field is a button labeled "Test connection".

Start by making sure that you can reach the service using these settings, by clicking the Test connection button. You should see the following message dialog.



A message dialog box with a blue circular icon containing a white lowercase 'i'. The text inside says "Connection to Site service worked". At the bottom right, there is an "OK" button.

You then need to click the Configuration button to set up the configuration of the Site Service. Refer to the table in the next section for more information on each field.



The image shows a 'Site Service configuration' dialog box with a title bar and a question mark icon. The main heading is 'Manage configuration settings for the given location'. It contains three sections: 'Database configuration', 'E-mail settings', and 'Centralized settings'. The 'Database configuration' section has fields for 'Connection type' (set to 'Named pipes'), 'Server host', 'Database name', 'Use Windows authentication' (checkbox), 'Database user' (set to 'sa'), 'Database password' (set to 'mydatabasepassword'), and 'Data area id' (set to 'LSR'). The 'E-mail settings' section has fields for 'Send interval (minutes)' (set to '0'), 'Batch size' (set to '25'), 'Maximum attempts' (set to '5'), and 'Truncate e-mail queue' (set to 'Delete e-mail after sending'). There is an 'SMTP settings' button. The 'Centralized settings' section has fields for 'External address', 'Private hash key', 'Connection pool size', and 'Max user connections'. At the bottom are three buttons: 'Get configuration', 'Send configuration', and 'Close'.

Site Service configuration

Manage configuration settings for the given location

Database configuration

Connection type: Named pipes

Server host:

Database name:

Use Windows authentication: ☐ Yes

Database user: sa

Database password: mydatabasepassword

Data area id: LSR

E-mail settings

Send interval (minutes): 0

Batch size: 25

Maximum attempts: 5

Truncate e-mail queue: Delete e-mail after sending

SMTP settings

Centralized settings

External address:

Private hash key:

Connection pool size:

Max user connections:

Get configuration Send configuration Close

Once you've filled out all the fields, click on **Send configuration** to send the configuration data to the Site Service. A restart of the service is required after each change.

## 3.2 Manual configuration

The configuration file is located by default in *C:\ProgramData\LS Retail\LS One Site Service*.

### 3.2.1 Image: Configuration text

```
<configuration>
  <appSettings>
    <add key="LogLevel" value="3" />
    <!-- ***** -->
    <!-- Settings that define if a synchronization service is used for dual displays and its timer interval -->
    <add key="UseDualDisplaySync" value="0" />
    <add key="DualDisplaySyncInterval" value="5" />
    <!-- ***** -->
    <!-- ***** -->
    <add key="DatabaseServer" value="localhost" />
    <add key="DatabaseWindowsAuthentication" value="true" />
    <add key="DatabaseUser" value="sa" />
    <add key="DatabasePassword" value="mydatabasepassword" />
    <add key="DatabaseName" value="mydatabase" />
    <!-- ***** -->
    <!-- DatabaseConnectionType can be one of the following: TCP/IP,Named pipes, Shared memory -->
    <!-- ***** -->
    <add key="DatabaseConnectionType" value="Named pipes" />
    <!-- ***** -->
    <!-- StoreControllerUser has to be created as a special server user on the Store Controller normal user will not work -->
    <add key="StoreControllerUser" value="StoreServerUser" />
    <add key="StoreControllerPassword" value="1234" />
    <add key="DataAreaID" value="LSR" />
    <add key="Port" value="9101" />
  </appSettings>
</configuration>
```



If using Windows 7 or later you need to start any editor as administrator to be able to change the configuration file.

After the configuration file has been changed, the LS One Site Service needs to be restarted.

The available settings in the “LS One Site Service.config” file are as follows:

Key	Default value
<b>LogLevel</b>	3
<b>DatabaseName</b>	mydatabase
<b>DatabaseWindowsAuthentication</b>	false
<b>DatabaseUser</b>	sa
<b>DatabasePassword</b>	mydatabasepassword
<b>DatabaseName</b>	mydatabase
<b>DataBaseConnectionType</b>	TCP/IP (Can also be Named pipes or Shared memory)
<b>StoreControllerUser</b>	StoreServerUser
<b>StoreControllerPassword</b>	1234
<b>Port</b>	9101

### 3.3 Common alterations:

- By default, only errors and exceptions are logged to the log file. To increase the amount of logging performed by the application, change the *LogLevel* settings to *1*. The log file (LSOneSiteService.log) is found in the install directory (see chapter 2.2).
- By default the service operates on port 9101. This can be changed by manipulating the *Port* setting.
- Database properties need to be set up. The settings parameters are exactly the same as in the Site Manager login configuration window.
- If using LS One Hosted environment then the Centralized settings need to be filled out.

## 4 LS One Site Service - Features

Currently the LS One Site Service contains features to give the LS One POS access to centralized data involving LS One Hospitality features, gift card features, loyalty point status, centralized suspension, centralized returns [and more](#).

## 5 Connecting the LS One POS

For the POS terminal to have access to LS Site Service, a Site Service profile needs to be configured and set on each terminal.

For more information on the [Site Service profile configuration](#) please go to the [LS One Online help](#)