



*International
Virtual
Observatory
Alliance*

Model Instances in Votables

Version 1.0

IVOA Working Draft 2020-09-15

Working group

DM

This version

<http://www.ivoa.net/documents/model-instance-in-vot/20200915>

Latest version

<http://www.ivoa.net/documents/model-instance-in-vot>

Previous versions

This is the first public release

Author(s)

François Bonnarel, Gilles Landais, Laurent Michel, Jesus Salgado,
Gerard Lemson

Editor(s)

Laurent Michel, Mark Cresitello Dittmar

Abstract

Vodml-instance-vot proposes a syntax to map VOTable data on any model serialized in VO-DML. Vodml-instance-vot annotations are grouped in a single XML block located in the VOTable head. The annotation block allows to easily reconstruct the model structure. It is designed in a way that the block can be reused on different data sets in order to facilitate the annotation process. Vodml-instance-vot is enabled to join data from different tables

Status of this document

This is an IVOA Working Draft for review by IVOA members and other interested parties. It is a draft document and may be updated, replaced, or obsoleted by other documents at any time. It is inappropriate to use IVOA Working Drafts as reference materials or to cite them as other than “work in progress”.

A list of current IVOA Recommendations and other technical documents can be found at <http://www.ivoa.net/documents/>.

Contents

1	Introduction	3
1.1	Role within the VO Architecture	3
2	Use Cases and Requirements	3
2.1	Use Cases	3
2.2	Requirements	3
3	Syntax	4
3.1	Mapping Block Structure	4
3.2	Syntax	5
3.2.1	VODML	5
3.2.2	MODEL	5
3.2.3	GLOBALS	5
3.2.4	TEMPLATES	5
3.2.5	COLLECTION	6
3.2.6	INSTANCE	7
3.2.7	ATTRIBUTE	8
3.2.8	REFERENCE	9
3.2.9	JOIN	9
3.2.10	WHERE	10
3.2.11	PRIMARY_KEY	10
3.2.12	FOREIGN_KEY	11
4	Changes from Previous Versions	11

Acknowledgments

CDS/TDIG/SourceDM contributors

PDF fallback.

Sorry - your ImageMagick (convert) does not support SVG import. If on Linux, installing librsvg2-bin should remedy this. Otherwise, please commit your SVG and ask the ivoatex creators to do the the conversion.

Figure 1: Architecture diagram for this document

Conformance-related definitions

The words “MUST”, “SHALL”, “SHOULD”, “MAY”, “RECOMMENDED”, and “OPTIONAL” (in upper or lower case) used in this document are to be interpreted as described in IETF standard RFC2119 (?).

The *Virtual Observatory (VO)* is a general term for a collection of federated resources that can be used to conduct astronomical research, education, and outreach. The *International Virtual Observatory Alliance (IVOA)* is a global collaboration of separately funded projects to develop standards and infrastructure that enable VO applications.

1 Introduction

1.1 Role within the VO Architecture

Fig. 1 shows the role this document plays within the IVOA architecture (?).

???? and so on, LaTeX as you know and love it. ????


2 Use Cases and Requirements

2.1 Use Cases

2.2 Requirements

3 Syntax

Element Hierarchy



Attribute Summary

VODML	MODEL name url	GLOBALS	TEMPLATES tableref	
INSTANCE dmrole ID	COLLECTION dmrole ID	REFERENCE dmrole tableref dmref	ATTRIBUTE dmrole dmtype ref value unit arrayindex	
PRIMARY_KEY ref dmtype value	FOREIGN_KEY ref	WHERE primarykey foreignkey value	JOIN tableref dmref	

3.1 Mapping Block Structure

```

<VOTABLE xmlns="http://www.ivoa.net/xml/VOTable/v1.3"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  version="1.4">
  <VODML>
    <MODEL> ... </MODEL>
    <GLOBALS> ... </GLOBALS>
    <TEMPLATES> ... </TEMPLATES>
    ...
  </VODML>
  ...

```

</VOTABLE>

Listing 1: Complete mapping block example

3.2 Syntax

3.2.1 VODML

Top level mapping element.

Element	Position	Cardinality
MODEL	1	1-*
GLOBALS	2	0-*
TEMPLATES	3	0-*

Table 1: Allowed children for VODML

3.2.2 MODEL

Attribute	Role
@name	Name of the mapped model (informal). This attribute cannot be left empty
@url	Url of the vo-dml serialization of the model. This attribute cannot be left empty if present.

Table 2: MODEL attributes

@name	@url	Pattern
MAND	OPT	Unique attribute pattern supported by MODEL

Table 3: Valid attribute patterns for MODEL

3.2.3 GLOBALS

Element	Position	Cardinality
INSTANCE Any	0-*	
COLLECTION	Any	0-*

Table 4: Allowed children for GLOBALS

3.2.4 TEMPLATES

Attribute	Role
@tableref	ID of the mapped table.

Table 5: TEMPLATES attributes

@tableref	Pattern
OPT	If @tableref is not present, TEMPLATES maps the first TABLE of the RESOURCE

Table 6: Valid attribute patterns for TEMPLATES

Element	Position	Cardinality	
WHERE	1	0-*	The mapping must be applied to the rows matching the WHERE condition only
INSTANCE	2	0-*	Mapped class instances

Table 7: Allowed children for TEMPLATES

3.2.5 COLLECTION

Attribute	Role
@ID	ID of the COLLECTION element, must be unique within the mapping block. Must not be left empty.
@dmrole	Role of the collection in the DM. Must not be empty if present

Table 8: COLLECTION attributes

@ID	@dmrole	Pattern
MAND	NO	The collection, usually located in GLOBALS, has no role. It can be referenced by a REFERENCE
OPT	MAND	The element maps a collection playing a role in the model. @ID can also be set in that case.

Table 9: Valid attribute patterns for COLLECTION

Element	Position	Cardinality	
REFERENCE	Any	0-*	Collection item as a reference to either a class or a collection instance. No JOIN allowed if present
INSTANCE	Any	0-*	Collection item as a class instance. No JOIN allowed if present
ATTRIBUTE	Any	0-*	Collection item as a simple attribute. No JOIN allowed if present
COLLECTION	Any	0-*	Collection item as a collection. No JOIN allowed if present
JOIN	1	0-1	The COLLECTION must be populated by a join operation. In this case JOIN must be the unique child of COLLECTION

Table 10: Allowed children for COLLECTION

3.2.6 INSTANCE

Attribute	Role
@ID	ID of the mapping element
@dmrole	Role of the instance in the DM
@dmtype	Class name

Table 11: INSTANCE attributes

@ID	@dmrole	@dmtype	Pattern
MAND	NO	MAND	The instance, usually located in GLOBALS, has no role. It can be referenced by a REFERENCE
OPT	MAND	MAND	The element maps a instance playing a role in the model. @ID can also be set in that case.

Table 12: Valid attribute patterns for INSTANCE

Element	Position	Cardinality	
REFERENCE	Any	0-*	Object attribute as a reference to either a class or a collection instance.
INSTANCE	Any	0-*	Object attribute as a class instance.
ATTRIBUTE	Any	0-*	Object attribute as a simple attribute.
COLLECTION	Any	0-*	Object attribute as a collection.

Table 13: Allowed children for INSTANCE

3.2.7 ATTRIBUTE

Attribute	Role
@dmrole	Role of the attribute in the DM
@dmtype	Type of the attribute in the DM
@ref	Reference of the FIELD or PARAM that has to be sued to set the ATTRIBUTE value.
@value	Default ATTRIBUTE value. This value is taken if there is no @ref attribute or if @ref cannot be resolved.
@unit	ATTRIBUTE unit. This is the unit in which the native value must be converted to be compliant with the model. This attribute is always optional.
@arrayindex	Index of the native value to be taken to set the ATTRIBUTE. Must be ignored if the native value is a single value. An error must be risen if @arrayindex is out of range.This attribute is always optional.

Table 14: ATTRIBUTE attributes

@dmrole	@dmtype	@ref	@value	Pattern
MAND	MAND	MAND	OPT	The ATTRIBUTE value must be set with the value of the element referenced by @ref. The @ref can not be resolved and @value is present, @value must taken as ATTRIBUTE value
MAND	MAND	NO	MAND	The ATTRIBUTE value must be set with @value

Table 15: Valid attribute patterns for ATTRIBUTE

3.2.8 REFERENCE

Complex pattern that must be detailed later in a specific section

Attribute	Role
@dmrole	Role of the referenced instance or collection in the DM
@tableref	ID of the <code>COLLECTION</code> to be joined with in case of using a <code>FOREIGN_KEY</code>
@dmref	ID of the referenced instance or collection

Table 16: REFERENCE attributes

@dmrole	@tableref	@dmref	Pattern
MAND	MAND	NO	This is the <code>FOREIGN_KEY</code> pattern. @tableref gives the ID of the <code>COLLECTION</code> to be joined with. In this case <code>REFERENCE</code> must have one <code>FOREIGN_KEY</code> child and the joined <code>COLLECTION</code> must have a <code>PRIMARY_KEY</code>
MAND	NO	MAND	Simple reference to either an <code>INSTANCE</code> or <code>COLLECTION</code> , usually searched in the <code>GLOBALS</code>

Table 17: Valid attribute patterns for REFERENCE

3.2.9 JOIN

Attribute	Role
@tableref	Reference of the table to be joined with.
@dmref	Reference of the <code>COLLECTION</code> (in <code>GLOBALS</code> to be joined with.

Table 18: JOIN attributes

@tableref	@dmref	Pattern
MAND	NO	The join is done against the table identified by @tableref
NO	MAND	The join is done against the <code>COLLECTION</code> identified by @dmref

Table 19: Valid attribute patterns for JOIN

Element	Position	Cardinality	
WHERE	1	0-*	Join condition

Table 20: Allowed children for JOIN

3.2.10 WHERE

Attribute	Role
@primarykey	FIELD identifier of the primary key column
@foreignkey	FIELD identifier of the foreign key column
@value	Literal value the @primarykey cell must match with

Table 21: WHERE attributes

@primarykey	@foreignkey	@value	Pattern
MAND	MAND	NO	2 tables join criteria: @primarykey = @foreignkey
MAND	NO	MAND	Simple join criteria: @primarykey = @value

Table 22: Valid attribute patterns for WHERE

3.2.11 PRIMARY_KEY

Attribute	Role
@ref	ID of the FIELD used as primary key
@dmtype	Type of the key
@value	Literal key value. Used when the key relates to a COLLECTION in the GLOBALS

Table 23: PRIMARY_KEY attributes

@ref	@dmtype	@value	Pattern
MAND	MAND	NO	The FIELD referenced by @ref is a primary key. This pattern is used within a TEMPLATES
NO	MAND	MAND	@value gives the key value. This pattern is used to set a primary key to a COLLECTION

Table 24: Valid attribute patterns for PRIMARY_KEY

3.2.12 FOREIGN_KEY

Attribute	Role
@ref	Only used in REFERENCE . Identifier of the FIELD that must match the primary key of the referenced collection

Table 25: FOREIGN_KEY attributes

4 Changes from Previous Versions

No previous versions yet.