

# Molecular Dynamics FF, Manual , version 0.2.2

December 3, 2011

# Contents

<b>1</b>	<b>Aim</b>	<b>3</b>
<b>2</b>	<b>Theory</b>	<b>4</b>
2.1	Molecular Dynamics . . . . .	4
2.2	Optimisation . . . . .	4
2.3	Phonons . . . . .	4
2.4	Electric-Field Gradient . . . . .	4
2.5	Radial distribution function . . . . .	4
2.6	Binary Mixture Lennar-Jones . . . . .	4
2.7	Kob-Andersen model . . . . .	4
2.8	Verlet list . . . . .	4
2.9	Units . . . . .	4
<b>3</b>	<b>Usage</b>	<b>4</b>
3.1	Minimum settings: the input file . . . . .	4
3.2	Minimum setting: standart output . . . . .	5
3.3	Miniumim setting : Output files . . . . .	6
3.4	Input file : Description . . . . .	7
3.4.1	&controltag . . . . .	7
3.4.2	&mdtag . . . . .	9
3.4.3	&configtag . . . . .	10
3.4.4	&fieldtag . . . . .	12
3.4.5	&proptag . . . . .	13
3.4.6	&opttag . . . . .	14
3.4.7	&vibtag . . . . .	15
3.4.8	&efgtag . . . . .	15
3.4.9	&msdtag . . . . .	17
3.4.10	&grtag . . . . .	17
3.4.11	&vacftag . . . . .	17
<b>4</b>	<b>Output files description</b>	<b>18</b>

# 1 Aim

Le but de ce document est de repertorier les differents algorithmes utilisés par MDFF. Notamment, definir les commandes (TAG) et leurs valeurs par défaut. Mais également, les références aux codes, articles originaux, livres dont sont extraits les différents algorithmes, ou preciser dans le cas contraire (i.e FMV!) ce que fait la routine point par point. Ce travail de documentation permettra de faciliter la découverte de bug qui independamment de ma volonté sont (et seront) forcément présents.

## 2 Theory

### 2.1 Molecular Dynamics

### 2.2 Optimisation

### 2.3 Phonons

### 2.4 Electric-Field Gradient

### 2.5 Radial distribution function

### 2.6 Binary Mixture Lennar-Jones

### 2.7 Kob-Andersen model

### 2.8 Verlet list

### 2.9 Units

## 3 Usage

MDFFonly needs one input file usually called control.F <sup>1</sup>

### 3.1 Minimum settings: the input file

The input file is composed of different sections. Each section is defined by `&SECTIONNAME` and `&END`. Everything outside the sections is ignored.

In MDFF, five sections are always required :

- `&controltag ... &end` → General control parameters for calculation
- `&mdtag ... &end` → General Molecular dynamics parameters.
- `&configtag ... &end` → Information on the configuration
- `&fieldtag ... &end` → Set the Force-Field.
- `&proptag ... &end` → Calculation of properties

Using this minimum settings (5 empty sections) the code runs with default values. It correspond to a molecular dynamics trajectory of 10 unit of times of a fcc lennard-jones crystal (256 atoms) at  $\rho = 1.0$  at  $T = 1.0$ . In the next section we show the standard output of this minimum setting.

---

<sup>1</sup>the .F extension permits to get nice colors with vim

[illegible]

=====

=====

5

```

density                                     =      1.0000
distance check subroutine
smallest distance =      1.12

```

```

=====

force field information :
no masses are implemented
LENNARD-JONES

```

$$V = \frac{\epsilon}{(q-p)^6} - \frac{\sigma^6}{r^6} - \frac{q}{r} + \frac{\sigma^6}{r^6} - \frac{p}{r^6}$$

```

USER DEFINED MODEL
cutoff =      2.50000

```

```

A-A interactions:
sigmaAA =      1.00000
epsAA   =      1.00000
qAA     =     12.00000
pAA     =      6.00000
long range correction :      -0.535433102

```

```

parallelisation - atom decomposition
rank   0 atom   1 to 256

```

```

...

```

```

TOTAL :  cpu time      0.15
MD :    cpu time      0.01

```

```

main subroutines:
MD:

```

```

engforce_bmlj      :  cpu time      0.01
engforce_coul_DS   :  cpu time      0.00
vnlistcheck        :  cpu time      0.00

```

### 3.3 Miniumim setting : Output files

For this minimum setting, the code generates 4 files:

- OUTFF : close to the standard output
- OSZIFF : thermodynamic parameters
- TRAJFF : trajectory file (empty in this case)
- CONTFF : final configuration

theses files and other output files are described in a following section.

### 3.4 Input file : Description

#### 3.4.1 &controltag

Where : SUBROUTINE control\_init in control.f90

Parameter	Type	Short Description	Default value
lbmlj	(LOGICAL)	set the binary mixture lennard-jones potential (see section 2.6)	.TRUE.
lcoulomb	(LOGICAL)	set coulombic potentials (to be tested)	.FALSE.
lvnlist	(LOGICAL)	use verlet neighbour list (see section 2.8)	.TRUE.
lstatic	(LOGICAL)	static calculation	.FALSE.
lpbc	(LOGICAL)	use periodic boundary conditions (if .FALSE. should be tested)	.TRUE.
lreduced	(LOGICAL)	reduced the output quantities by the total number of particules  Comment: this has nothing to do with the units of the calculated quantities Units are discussed in section 2.9	.TRUE.
lshiftpot	(LOGICAL)	use a shifted potential (maybe redundant with ctrunc)	.TRUE.
ltest	(LOGICAL)	get round of the main code (for test purpose only)	.FALSE.
lrestart	(LOGICAL)	restart calculation read previous positions and velocities	.FALSE.

<code>calc</code>	(CHARACTER)	<p><code>'md'</code> : molecular dynamics simulation (see section 2.1)</p> <p><code>'opt'</code> : unconstrained optimization of configuration saved in TRAJFF file (see section 2.2)</p> <p><code>'vib'</code> : <code>'vib+fvib'</code>, <code>'vib+gmod'</code>, <code>'vib+band'</code>, <code>'vib+dos'</code> : phonons related (see section 2.3)</p> <p><code>'efg'</code> : Electric Field Gradient calculation from configuration in TRAJFF (see section 2.4)</p> <p><code>'efg+acf'</code> : EFG auto-correlation function from EFGALL file (see section 2.4)</p> <p><code>'gr'</code> : radial distribution function of configurations in TRAJFF (see section 2.5)</p>	<code>'md'</code>
<code>dgauss</code>	(CHARACTER)	<p>algorithm for gaussian distribution (no fundamental differences test purpose only) (see section ??)</p> <p><code>'boxmuller_basic'</code> : also known as the cartesian form</p> <p><code>'boxmuller_polar'</code> : supposed to be faster than the basic method because it is simpler to compute.</p> <p><code>'knuth'</code> : knuth algorithm cited by [?]</p>	<code>'boxmuller_basic'</code>
<code>longrange</code>	(CHARACTER)	<p>algorithm for long-range interactions. It will be used for coulombic potential calculation and Electric-Field Gradient calculation, if both are set together.</p> <p><code>'direct'</code> : Direct summation (can be used for EFG but difficult to converge for columbic potential)</p> <p><code>'ewald'</code> : Ewald summation technique</p>	<code>'ewald'</code>
<code>cutoff</code>	(DBLE)	real-space cut-off for lennard-jones potentials	2.5
<code>skindiff</code>	(DBLE)	verlet-list cutoff ( cutoff + skindiff )	0.1



---

### 3.4.2 &mdtag

Where : SUBROUTINE md\_init in md.f90

Parameter	Type	Short Description	Default value
ltraj	(LOGICAL)	save trajectory in file TRAJFF	.FALSE.
integrator	(CHARACTER)	algorithm for dynamic integration (see section ??)  'nve-vv' : NVE velocity-verlet  'nve-lf' : NVE leap-frog  'nve-be' : NVE beeman  'nvt-and' : NVT Andersen  'nvt-nh' : NVT Nosé-Hoover  'nvt-nhc2' : NVT Nosé-Hoover two chains  'nve-lfq' : NVE leap-frog + equilibration	'nve-vv'
setvel	(CHARACTER)	velocity distribution  'MaxwBoltz' : Maxwell-Boltzmann distribution  'uniform' : Uniform distribution (test purpose)	'MaxwBoltz'
npas	(INTEGER)	total number of time steps	10
nequil	(INTEGER)	total number of equilibration steps	10
nequil_period	(INTEGER)	equilibration period	1

<b>nprint</b>	(INTEGER)	print thermo info to standard output and OUTFF (period)	1
<b>fprint</b>	(INTEGER)	print thermo info to file OSZIFF (period)	1
<b>itraj_start</b>	(INTEGER)	write trajectory from step <b>itraj_start</b>	1
<b>itraj_period</b>	(INTEGER)	write trajectory each <b>itraj_period</b> steps	10000
<b>spas</b>	(INTEGER)	save configuration each <b>spas</b> steps in file CONTF	1000
<b>dt</b>	(DBLE)	time step for integration	0.001
<b>temp</b>	(DBLE)	temperature	1.0
<b>nuandersen</b>	(DBLE)	characteristic frequency in andersen thermostat	NULL
<b>tauberendsen</b>	(DBLE)	characteristic time in berendsen thermostat (simple rescale if tauberendsen = dt )	<b>dt</b>
<b>Qnosehoover</b>	(DBLE)	Q parameter in Nose-Hoover two chains	NULL

### 3.4.3 &configtag

Where : SUBROUTINE config\_init in config.f90

Parameter	Type	Short Description	Default value
-----------	------	-------------------	---------------

<b>lgenconf</b>	(LOGICAL)	if <b>.TRUE.</b> generate the configuration if <b>.FALSE.</b> read configuration from file POSFF if <b>calc='md'</b> TRAJFF if <b>calc='opt'</b> or <b>'efg'</b> ISCFE if <b>calc='vib'</b>	<b>.TRUE.</b>
<b>lfcc</b>	(LOGICAL)	for <b>lgenconf=.TRUE.</b> generate face-centered cubic lattice	<b>.TRUE.</b>
<b>lsc</b>	(LOGICAL)	for <b>lgenconf=.TRUE.</b> generate simple cubic lattice (primitive)	<b>.FALSE.</b>
<b>lbcc</b>	(LOGICAL)	for <b>lgenconf=.TRUE.</b> generate body-centered cubic lattice	<b>.FALSE.</b>
<b>system</b>	(CHARACTER)	system name	<b>'UNKNOWN'</b>
<b>struct</b>	(CHARACTER)	crystal structure for fcc (only make sense for <b>ntype=2</b> ) <b>'NaCl'</b> <b>'random'</b>	<b>'random'</b>
<b>ntype</b>	(INTEGER)	number of types =1 or =2	<b>1</b>
<b>natm</b>	(INTEGER)	total number of atoms	<b>NULL</b>
<b>ncell</b>	(INTEGER)	number of cell in 1D (with <b>lfcc,lsc,lbcc</b> )	<b>4</b>
<b>xna</b>	(DBLE)	relative composition of atom of type A	<b>1.0</b>

<b>xnb</b>	(DBLE)	relative composition of atom of type B	0.0
<b>rho</b>	(DBLE)	density number ( if <b>box</b> =0.0 )	NULL
<b>box</b>	(DBLE)	lattice parameter ( if <b>rho</b> =0.0 )	NULL

#### 3.4.4 &fieldtag

Where : SUBROUTINE `field_init` in `field.f90`

Parameter	Type	Short Description	Default value
<b>lKA</b>	(LOGICAL)	use the Kob-Andersen model for BMLJ2.7	.FALSE.
<b>ctrunc</b>	(CHARACTER)	truncation and shift of the potential  'linear': linear correction (potential discontinuity at $r = r_{cut}$ )  'quadratic': quadratic correction ( potential and force discontinuity at $r = r_{cut}$ )	'linear'
<b>ncelldirect</b>	(INTEGER)	number of neighboring cells in the direct summation (total number of cells = $ncelldirect^3$  for <code>lcoulomb=.TRUE.</code> and <code>longrange='direct'</code>  not efficient for coulombic interaction	2
<b>ncellewald</b>	(INTEGER)	number of kpoints in the reciprocal contribution of the Ewald summation (total number of cells = $ncellewald^3$  for <code>lcoulomb=.TRUE.</code> and <code>longrange='ewald'</code>	10

<code>alphaES</code>	(DBLE)	Ewald screening parameter	1.0
<code>epsXY</code>	(DBLE)	depth of the potential well of the Lennard jones potential. XY = AA, BB or AB	1.0
<code>sigmaXY</code>	(DBLE)	finite distance at which the inter-particle potential is zero. XY = AA, BB or AB	1.0
<code>qljXY</code>	(DBLE)	exponent of the repulsive part. XY = AA, BB or AB	12
<code>pljXY</code>	(DBLE)	exponent of the attractive part. XY = AA, BB or AB	6
<code>mX</code>	(DBLE)	mass of the particle. X= A or B (not used)	1.0
<code>qX</code>	(DBLE)	charge of the particle. X= A or B	qA = 1.0 qB = -1.0

### 3.4.5 &proptag

Where : SUBROUTINE `prop_init` in `prop.f90`

Parameter	Type	Short Description	Default value
<code>lefg</code>	(LOGICAL)	calculate electric field gradient on the fly during the md	.FALSE.
<code>lgr</code>	(LOGICAL)	calculate radial distribution function on the fly during the md	.FALSE
<code>lstrfac</code>	(LOGICAL)	calculate static structural factor on the fly during the md	.FALSE
<code>lmsd</code>	(LOGICAL)	calculate mean square displacement on the fly during the md	.FALSE

<b>lvacf</b>	(LOGICAL)	calculate velocity autocorrelation function on the fly during the md	<b>.FALSE</b>
<b>nprop_start</b>	(INTEGER)	calculate properties from step <b>nprop_start</b>	<b>0</b>
<b>nprop</b>	(INTEGER)	calculate properties each <b>nprop</b> step ( for lgr and efg not sure anymore)	<b>1</b>
<b>nprop_print</b>	(INTEGER)	print properties each <b>nprop_print</b>	<b>nprop</b>

### 3.4.6 &opttag

Where : SUBROUTINE `opt_init` in `opt.f90`

Parameter	Type	Short Description	Default value
<b>optalgo</b>	(CHARACTER)	choose unconstrained optimization algorithm  'sastry' : Linear minimisation via cubic extrapolation of potential Original author S. Sastry JNCASR  'lbfgs' : Limited memory BFGS method for large scale optimisation Author: J. Nocedal <a href="#">[ref]</a>  'm1qn3' : M1QN3, Version 3.3, October 2009 Authors: Jean Charles Gilbert, Claude Lemarechal, INRIA. <a href="#">[ref]</a>	<b>step</b>
<b>ncopt</b>	(INTEGER)	number of configurations in TRAJFF	<b>0</b>
<b>nskipopt</b>	(INTEGER)	number of configurations skipped in the beginning	<b>0</b>
<b>nmaxopt</b>	(INTEGER)	number of configurations to be optimize	<b>1</b>

### 3.4.7 &vibtag

Where : SUBROUTINE vib\_init in vib.f90

Parameter	Type	Short Description	Default value
lwrite_vectff	(LOGICAL)	write the vector field (i.e eigenvectors) in VECTFF file	.FALSE.
ncvib	(INTEGER)	number of configurations in ISCF to be analysed	0
ngconf	(INTEGER)	number of configurations generated with calc='vib+gmod'	0
imod	(INTEGER)	if calc='vib+gmod' generate the mode imod	4
nkphon	(INTEGER)	number of kpoint between ks and kf used when calc = 'vib+band'	NULL
resdos	(DBLE)	resolution in vibrational density of states distribution	1.0
omegamax	(DBLE)	maximum value in dos	100.0
ksx,ksy,ksz	(DBLE)	first kpoint	NULL
kfx,kfy,kfz	(DBLE)	last kpoint	NULL

### 3.4.8 &efgtag

Where : SUBROUTINE efg\_init in efg.f90

Parameter	Type	Short Description	Default value
-----------	------	-------------------	---------------

<b>lefgprintall</b>	(LOGICAL)	whether or not we want to print all the efg for each atoms and configurations in file EFGALL	<b>.FALSE.</b>
<b>lefg_it_contrib</b>	(LOGICAL)	if one wants to get the contribution to EFG separated in types (only <b>'direct'</b> and test purpose)	<b>.FALSE.</b>
<b>ncefg</b>	(INTEGER)	number of configurations read in TRAJFF for EFG calculation ( <b>calc='efg'</b> )	<b>0</b>
<b>ntcor</b>	(INTEGER)	maximum number of steps for the efg auto-correlation function( <b>calc='efg+acf'</b> )	<b>10</b>
<b>ncellewald</b>	(INTEGER)	number of kpoints in the reciprocal contribution of the Ewald summation (total number of cells = $ncellewald^3$  for <b>longrange='ewald'</b>	<b>0</b>
<b>ncelldirect</b>	(INTEGER)	number of neighboring cells in the direct summation (total number of cells = $ncelldirect^3$  for <b>longrange='direct'</b> only	<b>0</b>
<b>cutefg</b>	(DBLE)	cut-off distance for efg calculation in for direct summation ( <b>longrange='direct'</b> )	<b>30.0</b>
<b>alphaES</b>	(DBLE)	Ewald sum screening parameter	<b>1.0</b>
<b>resvzz</b>	(DBLE)	resolution in vzz distribution	<b>0.1</b>
<b>reseta</b>	(DBLE)	resolution in eta distribution	<b>0.1</b>
<b>resu</b>	(DBLE)	resolution in Ui ditribution	<b>0.1</b>



<b>vzzmin</b>	(DBLE)	minimum value of vzz distribution which is then between [vzzmin, -vzzmin]	-4.0
<b>umin</b>	(DBLE)	minimum value of umin distribution which is then between [umin, -umin]	-4.0

### 3.4.9 &msdtag

Where : SUBROUTINE `msd_init` in `msd.f90` BE CAREFUL !!!

Parameter	Type	Short Description	Default value
<b>nblock</b>	(INTEGER)	????????? I forgot ;)	10
<b>ibmax</b>	(INTEGER)	????????? I forgot ;)	20
<b>tdifmax</b>	(DBLE)	????????? I forgot ;)	100.0

### 3.4.10 &grtag

Where : SUBROUTINE `control_init` in `radial_distribution.f90`

Parameter	Type	Short Description	Default value
<b>resg</b>	(DBLE)	resolution in the radial distribution function	

### 3.4.11 &vacftag

Where : SUBROUTINE `vacf_init` in `vacf.f90` BE CAREFUL

Parameter	Type	Short Description	Default value
-----------	------	-------------------	---------------

it0	(INTEGER)	???????? I forgot ;)	1
tdifmax	(DBLE)	???????? I forgot ;)	100.0

## 4 Output files description