



Simplicity Enhancements

ONTAP What's New

NetApp
December 08, 2020

This PDF was generated from https://docs.netapp.com/us-en/ontap-whatsnew/ontap98fo_simplicity_enhancements.html on July 29, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Simplicity Enhancements 1
 - System Manager Enhancements 1
 - REST API Enhancements 8
 - Upgrade and Tech Refresh Enhancements – ONTAP 9.8 10

Simplicity Enhancements

This section covers ONTAP 9.8 enhancements that improve simplicity. This includes the following:


- ONTAP System Manager updates
- ONTAP upgrade and tech refresh improvements
- REST API enhancements

System Manager Enhancements

ONTAP 9.7 introduced a revamp of the System Manager GUI, with the intention of simplifying the way admins manage ONTAP basic operations, such as storage provisioning and day-to-day operations. The new GUI also leverages REST APIs, which were added in ONTAP 9.6. In ONTAP 9.8, the System Manager classic view has been removed.

One of the major differences between the interfaces is the dashboard, which is the first page you reach when you first log in to NetApp ONTAP System Manager.

The following graphics show a side-by-side comparison of the classic and new versions of the System Manager dashboard.




When we look closer, we can see a few major differences.

Health/Alerts


When you first log into Classic System Manager, the top left corner has a list of cluster and node faults. These are summarized into clickable links. When you click one of the links, you get redirected to another page in System Manager.

You also had a separate area that shows the cluster HA state to see whether a node has failed over. In the following images, we see the dashboard view and what we see when we click on one of the links—in this case, our failed disks.



To see other alerts, you must navigate back to the dashboard, which takes time and extra clicks. One of the goals of the new System Manager view is to simplify this process.

The following figure shows the new System Manager dashboard. The two main differences for the health and alert views are that we now have the node HA state and alerts in the same window, and, rather than clicking away from the main dashboard, the alerts are now in a drop-down box.



Capacity Views

Extra clicks are also reduced for capacity views. In classic ONTAP System Manager, the capacity and storage efficiency ratios were found under Cluster Overview and had tabs to click around to find information. The new System Manager view consolidates the storage efficiency ratios and capacity views into a single graphic.




The new UI leverages logical used space and physical available space.


ONTAP System Manager Classic



ONTAP System Manager 9.8




The data protection views have been moved to their own dashboard under Protection. This page provides deeper, more granular looks at the data protection in the cluster and also provides a location to leverage the new SnapMirror Business Continuity (SM-BC).



Network Visualization


ONTAP System Manager 9.8 also removes the Application and Objects view in favor of a new Network Visualization view that shows network topology for the cluster, as well as red X's when a port is down.



Performance Views

Performance data graphs in System Manager now retain data for the cluster up to 1 year, rather than having classic System Manager performance data only be available while you are logged in. In ONTAP System Manager 9.8, you can now click on the hour, day, week, month, or year. There is also a way to download performance data to a CSV.

ONTAP System Manager Classic



ONTAP System Manager 9.8




File System Analytics

In high file- count environments, trying to find information about folder capacity, data age, and file counts usually requires time-intensive commands or scripts that run serial operations over NAS protocols, such as `ls`, `du`, `find`, and `stat`.

ONTAP System Manager 9.8 provides a way for admins to find out file system information in any NAS storage volume quickly and easily by enabling a low-impact scanner for each volume. This scanner crawls the ONTAP file system in the background with a low priority job and delivers a wealth of information that is available as soon as you navigate to a volume in System Manager 9.8 or later.

Enabling File Systems Analytics is as easy as navigating to the volume you want to scan. Go to Storage > Volumes and then use the search to find your desired volume. Click the volume, and then the Explorer tab.

From here, you see the Enable Analytics link on the right side of the page.



After you click enable, the scanner starts. The time of completion depends on the number of objects in the volume as well as the system load. After it is finished, you see the entire directory structure populated in the System Manager view. This view can be navigated down the directory tree, and it provides access for history information, directory size information, and file sizes.

The following figure shows views from the Tech_ONTAP volume in my cluster, which I use as an archive for

NetApp Tech ONTAP Podcast episodes.

Tech_ONTAP All Volumes

OverviewSnapshot CopiesSnapMirror (Local or Remote)Explorer

/ > Episodes

Graphical View

Directory Name	Used	Modify History	Access History
Episodes	30.4 GB		
> Insight 2016 - EMEA	4.1 GB		
> Episode 64 - Barcelona Recap	2.62 GB		
> Episode 65 - DevOps with the DevOpsFather Gene Kim	2.16 GB		
> Episode 66 - VCDX236	1.87 GB		
> Episode 1	1.71 GB		
> Episode 105 - CSA	1.1 GB		
> Episode 4	815 MB		
> Episode 170 - Active IQ	658 MB		
Episode 62 - Hardware Refresh	655 MB		
Episode 63 - Fabric Pools	649 MB		
> Episode 71 - SPC-1 A700s	624 MB		

When you click a folder, a file list appears on the right side of the page.

/ > Episodes > Episode 170 - Active IQ

Graphical View

Files

Show / Hide

Directory Name	Used	Modify History	Access History
Episodes	30.4 GB		
> Insight 2016 - EMEA	4.1 GB		
> Episode 64 - Barcelona Recap	2.62 GB		
> Episode 65 - DevOps with the DevOpsFather Gene Kim	2.16 GB		
> Episode 66 - VCDX236	1.87 GB		
> Episode 1	1.71 GB		
> Episode 105 - CSA	1.1 GB		
> Episode 4	815 MB		
> Episode 170 - Active IQ	658 MB		

Name	Size
ep170-meet-combined.output.mp3	57.7 MB
ep170-outro.output.mp3	195 KB
ep170-intro.output.mp3	103 KB
.DS_Store	6 KB
._DS_Store	4 KB

If you choose, you can enable Show Accessed Time to get a look at the last time a file was accessed.

Last Refreshed: Oct 22, 2020, 11:57:09 AM

Disable Analytics



Files

Name	Size	
ep170-meat-combined.output.mp3	57.7 MB	Wednesday, M...
ep170-outro.output.mp3	195 KB	Wednesday, M...
ep170-intro.output.mp3	103 KB	Wednesday, M...
.DS_Store	6 KB	Wednesday, M...
._DS_Store	4 KB	Wednesday, M...

Show / Hide

- ☒ Accessed Time
- ☒ Size

At the bottom of the page, you can see how much data hasn't been accessed in a year, as well as the directory and file counts in that folder.

Episode 170 - Active IQ (658 MB)

658 MB

Inactive
(accessed more than a year ago)

0 Bytes

Normal
(accessed in this year)

52 KB

Active
(accessed this week)

DIRECTORIES
10

FILES
141

NEWEST
2020 - WEEK 43

OLDEST
2019 or OLDER

In addition to being able to quickly find file sizes and directory information, this feature also provides information that can help you decide whether NetApp FabricPool technology would be effective in reducing the amount of cold data that is taking up space on your aggregates.

Active NFS Clients

ONTAP 9.7 introduced a way to see which NFS clients were accessing specific volumes in a cluster, as well as which data LIF IP addresses were in use with the `nfs connected-clients` command. This command is covered in detail in [TR-4067: NetApp ONTAP NFS Best Practices and Implementation Guide](#). This command is useful for scenarios where you need to find out what clients are attached to the storage system, such as upgrades, tech refreshes, or simple reporting.

ONTAP System Manager 9.8 offers a way to see these clients with the GUI, as well as a way to export the list to a .csv file. Navigate to Hosts > NFS Clients and you see a list of NFS clients that were active in the past 48 hours.



ONTAP System Manager		Search actions, objects, and pages			
NFS Clients (active in the past 48 hours)				Show / Hide Download Filter	
Client IP Address	Last Access	Storage VM	NFS Version	Data Network Interface	Volume
10.193.67.205	1 day 11 hour 16 minutes 25 seconds	DEMO	nfs3	10.193.67.219	ldbtestdata
10.193.67.205	1 day 11 hour 16 minutes 25 seconds	DEMO	nfs3	10.193.67.219	postgresql2_fg
10.193.67.205	1 day 11 hour 16 minutes 25 seconds	DEMO	nfs3	10.193.67.219	postgresql_fg
10.193.67.205	1 day 11 hour 16 minutes 25 seconds	DEMO	nfs3	10.193.67.219	testdata
10.193.67.205	1 day 11 hour 16 minutes 25 seconds	DEMO	nfs3	10.193.67.219	testdata_export
10.193.67.225	1 day 19 hour 29 minutes 22 seconds	DEMO	nfs3	10.193.67.219	filegroup05
10.193.67.225	1 day 19 hour 29 minutes 1 seconds	DEMO	nfs3	10.193.67.219	netappcp_vrbencos
10.193.67.225	1 day 19 hour 28 minutes 59 seconds	DEMO	nfs3	10.193.67.219	netgroup
10.193.67.225	1 day 19 hour 28 minutes 59 seconds	DEMO	nfs3	10.193.67.219	vsroot
10.193.67.178	8 hour 35 minutes 43 seconds	DEMO	nfs3	10.193.67.237	scripts
10.193.67.196	8 hour 33 minutes 43 seconds	DEMO	nfs3	10.193.67.237	scripts
10.193.67.205	1 day 11 hour 13 minutes 5 seconds	DEMO	nfs3	10.193.67.237	postgresql2_fg
10.193.67.225	1 day 19 hour 28 minutes 18 seconds	DEMO	nfs3	10.193.67.237	filegroup05
10.193.67.225	1 day 19 hour 28 minutes 34 seconds	DEMO	nfs3	10.193.67.237	home
10.193.67.240	21 seconds	DEMO	nfs3	10.193.67.237	postgresql_fg
10.193.67.178	8 hour 35 minutes 43 seconds	NFS	nfs3	10.193.67.214	netappcp_jdbfickets
10.193.67.176	59 minutes 2 seconds	ch-qum-mixed1	nfs4.1	10.193.67.112	vol_fc_origin
10.193.67.176	59 minutes 2 seconds	ch-qum-mixed1	nfs4.1	10.193.67.112	vol_unix

Other System Manager 9.8 Enhancements

ONTAP 9.8 also brings the following enhancements to System Manager:

<ul style="list-style-type: none"> NAS file security tracing (trace file access to troubleshoot permissions) Login banner configuration (banner that shows when you log in) MetroCluster configuration Logging level (adjust the level of logging done on the cluster) SAML configuration Onboard Key Manager NVMe subsystem Automatic aggregate provisioning and capacity expansion REST API support for ONTAP image upload Automatic port placement SnapMirror restore and reverse resync 	<ul style="list-style-type: none"> Disk assignment FabricPool enhancements (tiering policies and object tagging) Adding nodes to the cluster Direct nondisruptive upgrade to n+2 ONTAP releases (2-year window) Performance views per protocol S3 protocol management Multiple LUNs in the same volume Multiple LUN moves Single-click firmware updates SnapMirror Business Continuity support Storage efficiency policies Volume management enhancements
--	---

The following figure shows MetroCluster and single-click firmware updates.



REST API Enhancements

REST API support, added in ONTAP 9.6, enables storage admins to leverage industry standard API calls to ONTAP storage in their automation scripts without needing to interact with the CLI or GUI.

REST API documentation and samples are available with System Manager. Simply navigate to the cluster management interface from a web browser and add `docs/api` to the address (using HTTPS).

For example:

<https://cluster/docs/api>

This page provides an interactive glossary of available REST APIs, as well as a method to generate your own REST API queries.

ONTAP REST API ^{v1}

[Base URL: /api]
<https://ontap9-tme-8040.ntap2016.local/docs/api/swagger.yaml>

ONTAP adds support for an expansive RESTful API. The documentation below provides information about the types of API calls available to you, as well as details about using each API endpoint. You can learn more about the ONTAP REST API and ONTAP in the ONTAP 9 Documentation Center: <http://docs.netapp.com/ontap-9/topic/com.netapp.doc.dot-rest-api/home.html>. NetApp welcomes your comments and suggestions about the ONTAP REST API and the documentation for its use.

Using the ONTAP REST API online documentation

Each API method includes usage examples, as well as a model that displays all the required and optional properties supported by the method. Click the *Model* link, available with each API method, to see all the required and optional properties supported by each method.

Features for all ONTAP APIs

▼ Getting started with the ONTAP REST API

Overview

Let's review some key things about RESTful APIs and how they're implemented in ONTAP:

- REST API URLs identify the resources that you'll be working with, including clusters, SVMs, and storage.
- REST APIs use HTTP methods GET, POST, PATCH, DELETE, and OPTIONS to indicate their actions.
- REST APIs return common HTTP status codes to indicate the results of each call. Additional error details can be included in the results body.
- REST APIs request and response bodies are encoded using JSON.
- REST APIs support hyperlinking among resources using the Content-Type "application/hal+json".
- GET calls on collections usually return only name and UUID by default. If you want to retrieve additional properties, you need to specify them using the "fields" query parameter.
- ONTAP supports query-based DELETE or PATCH for all collection endpoints.
- If you're already familiar with the ONTAPI API (also known as ZAPI), there are some similarities between ONTAP REST APIs and ONTAPI. For example:
 - Both support the same transport and security mechanisms.
 - Both paginate results based on either number of seconds or number of records.
 - Both support filtering the returned records based on property values.
 - Both support limiting the returned properties.
 - Both support concurrent requests. If ONTAP temporarily can't handle additional calls, it will respond with an HTTP error status code of 503.
- However, there are important differences between REST APIs and the ONTAP CLI and ONTAPI that you should understand as well:
 - In many cases, ONTAP REST APIs use different names for fields and features.
 - REST APIs do not expose infrequently used CLI parameters.
 - REST APIs do not treat the cluster or nodes as an SVM (aka Vserver).
 - REST GET APIs support specifying a maximum time before paginating results. However, the default time is 15 seconds for REST (instead of 90 seconds for ONTAPI).
 - REST APIs are generally ordered by UUID or ID, so a rename operation using the PATCH method doesn't change the path keys.
 - REST APIs use one or more of the following properties to identify a resource: "name", "uuid", "id".
 - REST APIs often execute the equivalent of multiple CLI commands in a single request.
 - REST API properties use underscores instead of hyphens between words.
 - REST API dates are always in ISO-8601 format.
 - REST API comparisons between enum values (for <, >, ranges, and order_by) are done alphabetically. (In CLI and ONTAPI, enum comparisons are done based on an internal value for the enum.)
 - REST API field '<c' queries exclude records where the specified field is not set. You can add "null" (eg: limit=<10|null) to also return records where the specified field is not set.

► HAL linking

► Query parameters

► Query-based PATCH and DELETE

► Record filtering

► Requesting specific fields

In ONTAP 9.8, REST APIs are now annotated with which version they were added, which helps simplify life when you are trying to keep your scripts working across multiple ONTAP versions.

cluster Manages clusters, nodes, jobs, and cluster software

DOC cluster

DOC /cluster

GET /cluster

Introduced in 9.6

POST /cluster

Introduced in 9.6

PATCH /cluster

Introduced in 9.6

DOC /cluster/chassis

GET /cluster/chassis

Introduced in 9.6

GET /cluster/chassis/{id}

Introduced in 9.6

DOC /cluster/firmware/history

GET /cluster/firmware/history

New in 9.8

The following table provides a list of new REST APIs in ONTAP 9.8.

Cluster <ul style="list-style-type: none">* Firmware history* Cluster licensing – capacity pools* Cluster licensing – license managers* Node metrics* Software image upload MetroCluster <ul style="list-style-type: none">* Mediator* Diagnostics* Management/creation* DR groups* Interconnects* Nodes* Operations Networking <ul style="list-style-type: none">* Ethernet port metrics* Switch port information* Switch information* FC interface metrics* BGP peer groups* IP interface metrics* LIF service policies SAN <ul style="list-style-type: none">* NVMe metrics	Security <ul style="list-style-type: none">* FIPS mode enable/disable* Data encryption enable/disable* Azure Key Vaults* Google GCP-KMS* IP Sec Storage <ul style="list-style-type: none">* File copy/move* NetApp FlexCache® PATCH/modify* Monitored files* Snapshot policies* Storage efficiency policies* File and directory management (Async delete, QoS and File Systems Analytics) NAS <ul style="list-style-type: none">* Audit log redirect* CIFS sessions* File access tracing/Security trace Manage <ul style="list-style-type: none">* Event remediation Object Store/S3 <ul style="list-style-type: none">* S3 bucket management* S3 groups* S3 policies
--	---

For more information on System Manager updates in ONTAP 9.8 see the [Tech ONTAP Podcast Episode 266: NetApp ONTAP System Manager 9.8](#).

Upgrade and Tech Refresh Enhancements – ONTAP 9.8

Traditionally, ONTAP upgrades have had to happen within one or two major releases to work non-disruptively. For storage administrators who don't upgrade frequently, this becomes a major headache and logistical nightmare when it's finally time to upgrade ONTAP. Who wants to upgrade and reboot multiple times in a maintenance window?

ONTAP 9.8 now supports upgrades to ONTAP releases within a two-year window. This means if you want to upgrade from 9.6 to 9.8, you can do that directly without needing to go to ONTAP 9.7.


The following table provides a matrix of NetApp ONTAP version upgrades.

Starting Point	Direct Upgrade to:
ONTAP 9.6	ONTAP 9.7, ONTAP 9.8
ONTAP 9.7	ONTAP 9.8, ONTAP 9.n+2
ONTAP 9.8	ONTAP 9.n+1, ONTAP 9.n+2

This simplified upgrade process also provides a way for streamlined head upgrades. When a new hardware node is shipped, it has the latest ONTAP release installed. Previously, if your existing cluster was running an older ONTAP release, you had to either upgrade the existing nodes to the same ONTAP version as the new

node or you had to downgrade the new node to the older ONTAP release. And, as a further complication, if the newer hardware could not be downgraded, you were forced to take a maintenance window to upgrade the existing cluster.


With ONTAP 9.8's 2-year revision window, now you can add new nodes into a cluster that have ONTAP versions within that range and the old nodes automatically upgrade to the new ONTAP release in the background, using the nondisruptive aggregate relocation upgrade process.



This process also extends into cluster upgrades, where you want to swap out an entire HA pair from a cluster. With the ONTAP 9.8 2-year revision window and nondisruptive volume moves, this is now possible.

The basic steps are as follows:

1. Connect the new systems to an existing cluster, with ONTAP versions within a 2-year window.
2. Use nondisruptive volume move to evacuate the nodes.
3. Unjoin the old nodes from the cluster.



Next: Data Protocols

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.