

A Compendium of Mead Knowledge

Kyle Byerly

November 10, 2011



This work is licensed under the Creative Commons Attribution-ShareAlike 3.0 Unported License. To view a copy of this license, visit <http://creativecommons.org/licenses/by-sa/3.0/> or send a letter to Creative Commons, 444 Castro Street, Suite 900, Mountain View, California, 94041, USA.

Contents

1	Fermentation	5
1.1	Yeast	5
1.2	Yeast Nutrients	5
1.3	Yeast Feeding	6
1.3.1	Guidelines	6
1.3.2	Calculating YAN	6
1.4	Yeast Pitching Rate	6
1.5	Stirring	6
1.5.1	Stirring Schedule	6
1.5.2	Stirring Schedule with Fruit	6
1.5.3	Tricks and Tips for Stirring	6
1.6	H ₂ S and Mercaptans	7
1.6.1	Eliminating Before 2/3 Sugar Break	7
1.6.2	Eliminating After 2/3 Sugar Break	7
1.6.3	Eliminating After Fermentation is Complete	7
1.7	Temperature control	7
1.8	Oxygenation	8
1.9	Must pH	8
1.9.1	H ₂ S or Sluggish Fermentation	8
1.10	Step Feeding	9
1.10.1	Classical Step Feeding	9
1.10.2	Bottom Dwelling Continuous Diffusion Yeast Feeding (BDC DYF)	9
2	Honey	9
3	Spices	9
3.1	While Aging	9
3.2	Tinctures	9
3.2.1	Alcohol Tinctures	9
3.2.2	Water Tinctures	9
4	Oak	9
4.1	Benefits	9
4.2	Barrels	9
4.3	Cubes, Chips, and more	9
5	Fruit	9
6	Fermentation Vessels	9
6.1	Carboys	9
6.2	Kegs	9
6.3	Connicals	9
6.4	Buckets	9
7	Sanitation	9
8	Aging	9
8.1	Bulk Aging	9
8.2	Bottle Aging	9

9	Recipes	9
9.1	General Process	9
9.2	Dry Traditional	10
9.3	Semi-Sweet Traditional	10
9.4	Sweet Traditional	11
9.5	Semi-Sweet Session Mead	11

1 Fermentation

This is perhaps the most important aspect of mead making. You can have the best ingredients, but if you don't have a healthy fermentation, your honey, and other ingredients, won't shine. This section is ordered in approximate order of the magnitude of impact. The farther you read and apply, the better your meads will go. The earlier topics have more "bang for your buck" and are usually quite easy to implement.

Nutrient addition and yeast pitching rates are quite easy to implement. Temperature control can be done quite low-tech (with manual effort) or high-tech with automation. Oxygen stones aren't incredibly cheap but they do have a fair bit of benefit. The usage of pH meters, while relatively expensive, can give you quite a bit of useful information on the current status of your mead.

1.1 Yeast

There is a vast variety of high quality yeasts available to the average meadmaker. Highlighted below are a few of the favorite more easily available ones. In general, the best results from a given yeast are usually obtained when fermenting in the lower third of the yeast's fermentation temperature range.

D-47: A classic yeast for white wines which is often used to great effect in traditionals. Be careful of letting it get too warm (above 70°F) as it throws off fusels and harsh alcohols. It can Sur Lie (age on yeast) for quite some time, adding floral characteristics.

DV10: A champagne isolate of a bayanus strain that produces minimal esters and phenols. Also tends to not blow off more delicate honey aromas. Ferments to 18% regularly. Good for dry meads and high alcohol sweet meads. It is a low nutrient yeast, but tends to produce sulfur unless front-loaded with nutrients (50/25/25 schedule or 75/25 seems to work well).

71B-1122: Narbonne yeast that can metabolize some malic acid. Useful for young meads (low alcohol) or those with a significant portion of an acidic fruit.

K1V-1116: A generic fruit wine yeast. Good results have been reported in high temperature fermentation environments such as in excess of 75°F.

Uvaferm 43: A bayanus yeast strain that has an alcohol tolerance of 18%+. It is commonly used for high alcohol wines and tends not to blow off delicate aromas. Also commonly used with dessert wines and stuck fermentations.

1.2 Yeast Nutrients

Nutrients are used to make up for the lack of proper nutrients in the must, to aid in fermentation speed, or to overcome a stuck fermentation. They are typically added in relatively small amounts throughout the fermentation process. Because of the small amount needed, adding too much can be done easily, so care should be taken when calculating and adding nutrients to the must.

GO-FERM: Used in rehydrating yeast. 1.25g of GO-FERM per gram of yeast with 17g grams of water. Mix GO-FERM and water together and add yeast at re-hydration temperature (typically 104-109°F).

DAP: Also known as Di-ammonium phosphate, chemical name $(\text{NH}_4)_2\text{HPO}_4$ is a source of inorganic nitrogen, which provides YAN (Yeast Available Nitrogen) for nitrogen deficient musts (such as honey). 1g/L provides 210ppm of YAN. 1g/Gallon provides 50ppm of YAN. Do not add past 2/3 sugar break. The yeast cannot consume the nutrient at this stage and it will likely result in Urea type aromas and flavors in the finished mead. Do not add to hydrating yeast as DAP is somewhat toxic to re-hydrating yeast.

Fermaid K: Provides micro-nutrients and YAN for yeast health. Pyridoxine and Pantothenate are two of these micro-nutrients. 1g/Gallon provides 25ppm of YAN.

Yeast Hulls: also called Yeast Ghosts, are dried yeast cells. Used to aid in unsticking of a stuck fermentation or to combat H_2S formation at the end of a fermentation (usually past 2/3 sugar break).

1.3 Yeast Feeding

The process of yeast nutrient additions is relatively simple at the core. Yeast need nutrients and honey does not have enough, therefore small amounts of nutrients need to be added in order to keep the fermentation healthy. The Nanaïomo Winemakers have additional detail on nutrient addition for fermentation [1].

It is a very good idea to mix powders in liquids that you plan on putting into a fermenting liquid. Adding a powder to a fermenting liquid will introduce nucleation points which will in turn produce lots of foam. Mixing the powder into the foam allows one to gently stir the mix into the must without huge amounts of foam.

1.3.1 Guidelines

There isn't a set amount of nutrients to add, although there are guidelines. One of the easier (and common) to use nutrient combinations is Fermaid K and DAP at a ratio of 70% Fermaid K and 30% DAP[7]. Ratio is based on weight.

1.3.2 Calculating YAN

1.4 Yeast Pitching Rate

Yeast need to be pitched at the proper rate in order to have a high enough cell count to ferment cleanly. There are numerous calculator online, although most are focused on beer. Generally, one 8g packet of yeast is enough to properly ferment a 5 gallon batch of an under 1.120 O.G. mead. If over 1.120 O.G. pitching two packets is recommended.

Sometimes a starter is necessary. The ideal starter for wine yeast is generally 1.070. Using a stir plate is generally a good idea since it oxygenates and stirs, which keeps the yeast in solution and pushes off CO₂.

1.5 Stirring

Something as simple as stirring during fermentation can be one of the most important steps in producing an amazing mead. Stirring drives off CO₂ which is a toxin to yeast. It mixes together the yeast and the must, bring the yeast back into suspension, thus making it more readily able to consume the sugars. It also allows a slight mixing in of oxygen which is necessary for yeast growth. Mixing makes it easy to add your nutrients. Having a touch-point with your mead often makes it easy to check for H₂S or other issues.

Stirring tends to make fermentations faster and healthier.

There is a higher risk of infection with frequent stirrings. However, if you are careful with sanitation and keep your fermentation area clean, the risk is minimal. The rewards of a proper stirring schedule far outweigh the risks of infection.

1.5.1 Stirring Schedule

The easiest schedule to follow for a traditional mead is every 12 hours until 50% sugar break or 2/3 sugar break. Stirring much past that tends to introduce oxygen at a stage that oxygen is less than ideal. You also want to let the yeast drop at some point.

1.5.2 Stirring Schedule with Fruit

1.5.3 Tricks and Tips for Stirring

Get a drill attached stirring device.

When beginning to stir, start slowly so as not to be overwhelmed by foam.

Put a Star-San soaked rag around the top of the carboy or under the drill to help prevent infection or particles from the drill dropping into your mead.

1.6 H₂S and Mercaptans

One of the simplest indicators of yeast stress is the production of H₂S. H₂S smells of rotten eggs or sulfur. Yeast stress indicates that there is something off in the fermentation dynamics. The most common reason for H₂S is low nutrients. Other causes are temperature (either too low or too high for the yeast) and pH (too low or too high).

1.6.1 Eliminating Before 2/3 Sugar Break

The easiest thing to add here is DAP. If you've added no DAP or Fermaid K you should add a 70/30 mix of Fermaid K and DAP. Add at a dosing rate of [RATE], stir and the H₂S should lessen in under 5 minutes. If it doesn't, then add [RATE] and stir again. If, at this point, it is still smelling of H₂S then the issue is likely not because of lack of nutrients, but rather from a low pH, low temperature, or insufficient yeast pitching rate. It should be noted that it is often quite easy to test for pH or temperature before adding nutrients.

1.6.2 Eliminating After 2/3 Sugar Break

If you smell H₂S after 2/3 sugar break you should not use DAP or fermaid K to remedy the situation. Both of those contain inorganic nitrogen (DAP) that the yeast can't metabolize very well at that point of the fermentation. The best thing to add is Yeast Hulls at .2g to .9g per Gallon. Start with .2g/Gallon, and then, if after stirring and waiting 5 minutes the H₂S smell doesn't go away, add additional Yeast Hulls in .2g/Gallon increments (stirring and waiting inbetween additions).

1.6.3 Eliminating After Fermentation is Complete

If all else fails, and there's still H₂S in your mead after the fermentation is done you still have a chance of fixing the mead. It is more difficult and must be caught and fixed quickly. The earlier you catch the H₂S and deal with it, the less mercaptans you'll have in your mead.

Grapestompers[5] recommends sulfiting and doing what is often called "Splash Racking." This is a technique to aerate the sulfited mead to blow off the H₂S. If that's not sufficient to remove the H₂S it is recommended to rack the mead over copper.

The British Columbia Amatuer Winemakers Association[6] recommends aerating and racking the wine through a one inch PVC pipe with copper pot scrubbers inside, mentioning that the surface area is critical. They also do not recommend waiting, but doing the aeration and copper treatment as soon as possible as H₂S is converting to sulfides and then disulfides within 2 days of the beginning of H₂S production.

You will also likely want to fine and/or filter your mead after using copper as some report a decrease in shelf life of beverages treated with Copper.[CITATION NEEDED]

1.7 Temperature control

This is a very important part of a proper fermentation. In general you want to keep the temperature to the bottom 1/3 of the temperature range of the chosen yeast. This tends to produce the cleanest flavor profile with the least amount of fusels and other off flavors. Increasing the temperature tends to speed up the fermentation. It can also help kickstart struggling fermentations. If the temperature is too low fermentation will slow, or even completely stop.

1.8 Oxygenation

1.9 Must pH

[This section on pH is a work in progress and may contain wrong information]

Important in maintaining a healthy fermentation. Keeping the pH between 3.7 and 4.6 for initial fermentation is key.

1.9.1 H₂S or Sluggish Fermentation

If you're finding that your mead is producing a large amount of H₂S and that temperature, and/or Yeast Hull or nutrient additions are not eliminating it, chances are your pH is off. You will need to measure your pH to see if that is the cause. If you can measure your pH and it is below 3.5 then you'll want to add some CaCO₃ (Calcium Carbonate) at [DOSING RATE] until you've reached a pH of 3.7. If your pH is too high, above 4.8, you can add some acid blend to adjust below 4.6. There are issues with using too much acid blend or CaCO₃.

If your temperatures are outside the recommended yeast temperature range, slowly adjust the temperatures up or down with a water bath with ice to cool or warm water and/or a heating device such as a fermwrap or brewbelt. You'll want to slowly adjust the temperature, going fast will likely shock the yeast which could stop fermentation. Generally, changing the temperature of the must/mead faster than RATE] can make the yeast drop out and end fermentation.

1.10 Step Feeding

1.10.1 Classical Step Feeding

1.10.2 Bottom Dwelling Continuous Diffusion Yeast Feeding (BDC DYF)

2 Honey

3 Spices

3.1 While Aging

3.2 Tinctures

3.2.1 Alcohol Tinctures

3.2.2 Water Tinctures

4 Oak

4.1 Benefits

4.2 Barrels

4.3 Cubes, Chips, and more

5 Fruit

6 Fermentation Vessels

6.1 Carboys

6.2 Kegs

6.3 Connicals

6.4 Buckets

7 Sanitation

8 Aging

8.1 Bulk Aging

8.2 Bottle Aging

9 Recipes

9.1 General Process

Mix your honey with some warm water (in order to make the honey easier to work with). Gradually add cool water until you've reached your volume. Make sure the honey and water is completely mixed. At

this point take a gravity reading. If you're shooting for a gravity add honey or water if you're gravity is low or high respectively. Keep in mind that the sugar in honey varies from year to year and hive to hive.

At this point you should create your 109°F water for rehydrating your yeast. You will also want to use GO-FERM when hydrating. Mix the water and GO-FERM, then add the yeast and let sit for 15-20 minutes. I recommend you cover the yeast with sanitized tinfoil.

Calculate your needed Fermaid-K and DAP additions. For 250ppm YAN (good for use with D47 where it'll go to 14% potential) you'll need 20.8g Fermaid-K and 9g of DAP. You'll add 16.6g Fermaid-K and 4.5g DAP at the end of the lag phase (when the yeast starts bubbling), and then the rest about 24 hours later. There are many schedules that spread the additions out over a longer time. Some claim that these are more effective. You do not want to add DAP (and Fermaid-K contains some DAP) past 66% sugar break (where 66% of the sugars have been consumed by the yeast).

Stirring is critical. It mixes up the yeast and honey mixture, blowing off toxic CO₂. It stabilizes the temperature and gives a good chance to check for H₂S. And it introduces just a little bit of O₂ which is needed for yeast growth. Stirring should be done twice a day until 66% sugar break. If you have fruit in your mead you will want to do what is known as knocking down the cap. This basically means you submerge the fruit layer that is sitting on top. Heat builds up in the fruit cap and can result in nasty off flavors from dying yeast. Ideally the cap should be knocked down 4-6 times a day. This can be accomplished with a quick stir, or with a sanitized spoon (if in a bucket for primary).

Three useful resources for when you are crafting a recipe are the Gotmead Mead Calculator[3], the Lallemend Yeast Chart[2], and the Nanaio Winemakers YAN Yeast Calculator[4].

9.2 Dry Traditional

Ingredients

12 – 14	lbs. Quality Honey
5	gal. water (to volume)
200 – 250	ppm YAN, depends on yeast chosen, 7:3::Fermaid-K:DAP
1	pkt. re-hydrated Yeast (D-47, DV10, 71B-1122, K1V-1116...)

Notes

This will make a standard strength dry mead. You'll want to shoot for around 1.085-1.100 for original gravity and look for a final gravity between 0.992 and 1.004 with final alcohol around 12-14% ABV.

9.3 Semi-Sweet Traditional

Ingredients

15 – 17	lbs. Quality Honey
5	gal. water (to volume)
200 – 250	ppm YAN, depends on yeast chosen, 7:3::Fermaid-K:DAP
1	pkt. re-hydrated Yeast D-47

Notes

This will make a standard strength semi-sweet mead. You'll want to shoot for around 1.110-1.120 for original gravity and look for a final gravity between 1.004 and 1.014 with final alcohol around 14% ABV. 1.004 is usually considered dry, but there can be some perceptual overlap. If it goes dry, you can always backsweeten by adding more honey. The reason this uses D-47 is because it is a 14% alcohol tolerant yeast and many of the others will take this all the way dry. If you use a stronger yeast, you may need to add more honey or backsweeten.

9.4 Sweet Traditional

Ingredients

18 – 21	lbs. Quality Honey
5	gal. water (to volume)
200 – 300	ppm YAN, depends on yeast chosen, 7:3::Fermaid-K:DAP
1	pkt. re-hydrated Yeast D-47

Notes

This will make a standard strength semi-sweet mead. You'll want to shoot for around 1.130-1.150 for original gravity and look for a final gravity between 1.025 and 1.045 with final alcohol around 14% ABV. The reason this uses D-47 is because it is a 14% alcohol tolerant yeast and many of the others will take this into semi-sweet or dry territory or into higher alcohol (and longer aging). If you use a stronger yeast, you may need to start with a higher gravity or backsweeten.

9.5 Semi-Sweet Session Mead

TODO

References

- [1] Nanaïomo Winemakers, Adding Nitrogen to Fermentations. <http://www.nanaimowinemakers.org/Winemaking/General/AddingNitrogen.htm>
- [2] Chart of Lallemend Yeasts. http://www.lallemendwine.us/products/yeast_chart.php
- [3] Gotmead's Mead Calculator http://www.gotmead.com/index.php?option=com_content&task=view&id=745&Itemid=16
- [4] Nanaïomo Winemakers, YAN Yeast Calculator <http://www.nanaimowinemakers.org/Winemaking/General/YAN-YEAST-Calc-Nov2010-rev2.xls>
- [5] Grapestompers, How to fix rotten egg smell in wine http://www.grapestompers.com/hydrogen_sulfide.asp
- [6] British Columbia Amatuer Winemakers Association, Hydrogen Sufffide and its Derivatives <http://www.bcawa.ca/winemaking/h2s.htm>
- [7] Gotmead Forums, Fermaid K Information, post by 'Oskaar' <http://www.gotmead.com/forum/showthread.php?t=12498>