

Package ‘gR2’

November 20, 2019

Type Package

Title Generalized R Square Measures for a Mixture of Bivariate Linear Dependences

Version 0.1.0

Author Jingyi Jessica Li, Heather J Zhou

Maintainer Jingyi Jessica Li <jli@stat.ucla.edu>, Heather J Zhou <heatherjzhou@ucla.edu>

Description This package implements the estimation and inference of generalized R square.

License GPL-2

Encoding UTF-8

LazyData true

Imports lmodel2, parallel, mvtnorm

RoxygenNote 6.1.1

R topics documented:

gR2	1
Index	4

gR2	<i>gR2</i>
-----	------------

Description

gR2 calculates the sample gR2 under the specified scenario, the unspecified scenario (K chosen), and the unspecified scenario (K not chosen). It also provides an option to perform statistical inference on the population gR2.

Usage

```
gR2(x, y, z = NULL, K = NULL, cand.Ks = 1:4, nstart = 30,  
    mc.cores = detectCores() - 1, regressionMethod = "MA",  
    inference = FALSE, conf.level = 0.95, method = "general")
```

Arguments

<code>x</code>	A numeric vector.
<code>y</code>	A numeric vector of the same length as <code>x</code> .
<code>z</code>	A vector of integers that represents the line membership of all the data points. Must be of the same length as <code>x</code> and <code>y</code> . Default is <code>NULL</code> .
<code>K</code>	Number of lines in the unspecified scenario. Default is <code>NULL</code> .
<code>cand.Ks</code>	A vector of positive integers that represents the candidate <code>K</code> 's in the unspecified scenario. Default is <code>1:4</code> .
<code>nstart</code>	Number of initializations for the K-lines algorithm in the unspecified scenario. Default is <code>30</code> .
<code>mc.cores</code>	Number of cores to use in the unspecified scenario. The default is the number of CPU cores minus one.
<code>regressionMethod</code>	Valid values are "MA" and "LM". Indicates which regression method to use in the K-lines algorithm - major axis regression or linear regression. Default is "MA".
<code>inference</code>	Logical. If <code>TRUE</code> , then a confidence interval for the population gR2 of confidence level <code>conf.level</code> will be calculated. Also will be calculated is a p-value of the hypothesis test where the null hypothesis is that the population gR2 is 0 and the alternative hypothesis is that the population gR2 is greater than 0. Default is <code>FALSE</code> .
<code>conf.level</code>	The confidence level of the confidence interval. See description of <code>inference</code> . Default is <code>0.95</code> .
<code>method</code>	Valid values are "general" and "binorm". Indicates which asymptotic distribution of the sample gR2 to use for inference. Default is "general".

Details

The arguments that require user input are `x` and `y`, which must be numeric vectors of the same length.

There are three broad types of scenarios: the specified scenario, the unspecified scenario (`K` chosen), and the unspecified scenario (`K` not chosen). The specified scenario is considered when `z` is provided; the unspecified scenario (`K` chosen) is considered when `z` is not provided but `K` is provided; and the unspecified scenario (`K` not chosen) is considered when neither `z` or `K` is provided.

In the unspecified scenario (`K` chosen), we recommend that users set `K` to be less than or equal to 4 for interpretability.

In the unspecified scenario (`K` not chosen), the `gR2` function will automatically choose a `K` value from `cand.Ks` using the Akaike information criterion (AIC). Two plots will be outputted: (1) a scree plot that shows how average squared perpendicular/vertical distance changes with the candidate `K`, and (2), a plot that shows how AIC changes with the candidate `K`. Users can decide whether the `K` value chosen by the `gR2` function is reasonable by checking these two plots.

Value

`gR2` returns a list consisting of one or more of the following items:

<code>estimate</code>	The sample gR2.
<code>conf.level</code>	The confidence level of the confidence interval (if <code>inference</code> is <code>TRUE</code>).
<code>conf.int</code>	The confidence interval for the population gR2 (if <code>inference</code> is <code>TRUE</code>).

p.val	The p-value of the hypothesis test where the null hypothesis is that the population gR2 is 0 and the alternative hypothesis is that the population gR2 is greater than 0 (if inference is TRUE).
K	The number of lines in the unspecified scenario, either chosen by the user or chosen from cand.Ks by the gR2 function.
membership	The inferred line membership of all the data points in the unspecified scenario.

Author(s)

Jingyi Jessica Li, <jli@stat.ucla.edu>

Heather J Zhou, <heatherjzhou@ucla.edu>

References

Li, J.J., Tong, X., and Bickel, P.J. (2018). Generalized R2 Measures for a Mixture of Bivariate Linear Dependences. arXiv.

Index

gR2, [1](#)