

Configuring 6to4 Tunnels (Optional – Not to be graded)

Equipments – Same as in the Preliminary Lab.
Each reservation is for a 2-hour period.

The Assignment:

The complete assignment follows this page. From the experience in the previous labs you should be able to make reservations and access the devices. Note that the assignment may not state every step (such as using *enable* to get into the privileged mode and *configure terminal* to get into the configuration mode. You should be able to figure that out from the handouts on Cisco configurations). It's a good idea to read through the assignment first and have a good understanding before attempting the lab. Have fun!

Deliverables (No need to submit but this is what I would ask for if this is to be graded):

- For steps include screen shots or outputs which demonstrate you have completed the step.
- When you are done with all the configurations, do a "show run" for each router and copy them into a text file.
- Please put all the above in a single file, or in separate files and submit a zip file.

Support:


- Useful information can be found under the Lab Resources link on <http://lanlab.cdm.depaul.edu>)
- If you encounter problems with the DLPods, please check the following pages first: [FAQs](#) and [Lab Documentation](#), as they provide guidelines for fixing some common problems.
- If a problem still cannot be solved after consulting the aforementioned pages, email an error report to lanlab@cdm.depaul.edu and cc me, achung@cdm.depaul.edu **Please clearly indicate the course (TDC 563) and lab number in the subject line.** Responses normally given during lab hours. Lab assistants will be available if you work in the lab.
- **Lab hours are: 12-10pm M-F, 12-6pm Sa and Su. You may work on the DL Pods any time, but lab assistants are only available during the lab hours.**

Lab 8-3 Configuring 6to4 Tunnels

Learning Objectives

- Configure EIGRP for IPv4
- Create a 6to4 tunnel
- Configure static IPv6 routes

Topology Diagram



Scenario

For this lab, you will configure EIGRP for full connectivity between all IPv4 subnets. Then you will create a 6to4 tunnel and create static routes to go over it.

Step 1: Lab Preparation

Erase your configurations and reload your routers. Once your routers are reloaded, set up the appropriate hostnames.

Step 2: Configure Loopbacks and Physical Interfaces

Configure the loopback interfaces with IPv4 addresses and IPv6 addresses where appropriate. Also configure the serial interfaces with the IPv4 addresses shown in the diagram. Set the clockrates on the appropriate interfaces and issue **no shutdown** on all serial connections. Verify that you have local subnet connectivity with **ping**.

```
R1(config)# interface loopback0
R1(config-if)# ip address 10.1.1.1 255.255.255.0
R1(config-if)# ipv6 address FEC0::1:1/112
R1(config-if)# interface serial0/F/0
R1(config-if)# ip address 172.16.12.1 255.255.255.0
R1(config-if)# clockrate 64000
R1(config-if)# no shutdown

R2(config)# interface loopback0
R2(config-if)# ip address 10.1.2.1 255.255.255.0
R2(config-if)# interface serial0/F/0
R2(config-if)# ip address 172.16.12.2 255.255.255.0
R2(config-if)# no shutdown
R2(config-if)# interface serial0/F/1
R2(config-if)# ip address 172.16.23.2 255.255.255.0
R2(config-if)# no shutdown

R3(config)# interface loopback0
R3(config-if)# ip address 10.1.3.1 255.255.255.0
R3(config-if)# ipv6 address FEC0::3:1/112
R3(config-if)# interface serial0/F/1
R3(config-if)# ip address 172.16.23.3 255.255.255.0
R3(config-if)# no shutdown
```

Step 3: Configure EIGRP

Configure EIGRP for AS 1 for the major networks 172.16.0.0 and 10.0.0.0 on all three routers. Make sure you disable auto-summarization. You should have full IPv4 connectivity after this.

```
R1(config)# router eigrp 1
R1(config-router)# no auto-summary
R1(config-router)# network 10.0.0.0
R1(config-router)# network 172.16.0.0

R2(config)# router eigrp 1
R2(config-router)# no auto-summary
R2(config-router)# network 10.0.0.0
R2(config-router)# network 172.16.0.0

R3(config)# router eigrp 1
R3(config-router)# no auto-summary
R3(config-router)# network 10.0.0.0
R3(config-router)# network 172.16.0.0
```

Step 4: Configure a Manual IPv6 Tunnel

A tunnel is a logical interface that acts as a logical connection between two endpoints. It is similar to a loopback interface in that there is no corresponding

physical interface, but it is different in that there is more than one router involved. A 6to4 tunnel uses special IPv6 addresses in the 2002::/16 address space. The first 16 bits are the hexadecimal number 2002, and the next 32 bits are the original source IPv4 address in hexadecimal form. A 6to4 tunnel does not require a destination address because it is not a point-to-point link.

In this lab, you will configure routers R1 and R3 for a 6to4 tunnel to provide IPv6 connectivity between their loopback interfaces. To configure a 6to4 tunnel, get the tunnel interface configuration prompt using the **interface tunnel number** command. For simplicity, use interface number 0.

Next, set the tunnel mode with the **tunnel mode ipv6ip 6to4** command. Then set up the IPv6 address with the **ipv6 address address/mask** command. The address for R1 is 2002:AC10:0C01:1::1/64, because AC10:0C01 corresponds to 172.16.12.1, with 172 being AC, 16 being 10, 12 being C, and 1 being 1. The 1 after this address is just a more specific subnet, and the 1 at the end is the host address. R3's address is 2002:AC10:1703:1::3/64. Notice that the two addresses are not in the same /64 subnet.

After setting the IPv6 addresses, set the source interface for the tunnel with the **tunnel source type/number** command. Now that all the tunnel settings are set, set up an IPv6 static route for the whole 2002::/16 with the global command **ipv6 route address/mask interface**, with the interface being the tunnel you just created. Verify that you can ping the other side of the tunnel once all the commands have been entered.

```
R1(config)# interface tunnel 0
R1(config-if)# tunnel mode ipv6ip 6to4
R1(config-if)# ipv6 address 2002:AC10:0C01:1::1/64
R1(config-if)# tunnel source serial0/F/0
R1(config-if)# exit
R1(config)# ipv6 route 2002::/16 tunnel0
```

```
R3(config)# interface tunnel 0
R3(config-if)# tunnel mode ipv6ip 6to4
R3(config-if)# ipv6 address 2002:AC10:1703:1::3/64
R3(config-if)# tunnel source serial0/F/1
R3(config-if)# exit
R3(config)# ipv6 route 2002::/16 tunnel0
```

```
R1#ping 2002:AC10:1703:1::3
```

```
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 2002:AC10:1703:1::3, timeout is 2 seconds:
!!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 64/67/68 ms
```

```
R3#ping 2002:AC10:C01:1::1
```

```
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 2002:AC10:C01:1::1, timeout is 2 seconds:
!!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 64/66/68 ms
```

Step 5: Configure Static IPv6 Routes

Just like IPv4, IPv6 can have static routes entered into its routing table. You already created one for the 2002::/16 network in Step 4. For this section of the lab, you will put a static route on R1 telling it how to get to R3's loopback address. On R3, you will put a static default route pointing to R1. Just like in IPv4, static routes with a next-hop IPv6 address are created with the **ipv6 route address/mask next-hop** command. The next hop for both routers is the IPv6 address of the other end of the tunnel. Before entering these commands, enable IPv6 routing with the **ipv6 unicast-routing** command. You can verify by using the **show ipv6 route** command or by pinging the remote loopback address from each router.

```
R1(config)# ipv6 unicast-routing
R1(config)# ipv6 route FEC0::3:0/112 2002:AC10:1703:1::3
```

```
R3(config)# ipv6 unicast-routing
R3(config)# ipv6 route FEC0::1:0/112 2002:AC10:C01:1::1
```

```
R1#show ipv6 route
```

```
IPv6 Routing Table - 8 entries
```

```
Codes: C - Connected, L - Local, S - Static, R - RIP, B - BGP
```

```
U - Per-user Static route
```

```
I1 - ISIS L1, I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary
```

```
O - OSPF intra, OI - OSPF inter, OE1 - OSPF ext 1, OE2 - OSPF ext 2
```

```
ON1 - OSPF NSSA ext 1, ON2 - OSPF NSSA ext 2
```

```
D - EIGRP, EX - EIGRP external
```

```
S 2002::/16 [1/0]
  via ::, Tunnel0
C 2002:AC10:C01:1::/64 [0/0]
  via ::, Tunnel0
L 2002:AC10:C01:1::1/128 [0/0]
  via ::, Tunnel0
L FE80::/10 [0/0]
  via ::, Null0
C FEC0::1:0/112 [0/0]
  via ::, Loopback0
L FEC0::1:1/128 [0/0]
  via ::, Loopback0
S FEC0::3:0/112 [1/0]
  via 2002:AC10:1703:1::3
L FF00::/8 [0/0]
  via ::, Null0
```

```
R3#show ipv6 route
```

```
IPv6 Routing Table - 8 entries
```

```
Codes: C - Connected, L - Local, S - Static, R - RIP, B - BGP
```

```
U - Per-user Static route
```

```
I1 - ISIS L1, I2 - ISIS L2, IA - ISIS interarea, IS - ISIS summary
```

```
O - OSPF intra, OI - OSPF inter, OE1 - OSPF ext 1, OE2 - OSPF ext 2
```

```
ON1 - OSPF NSSA ext 1, ON2 - OSPF NSSA ext 2
```

```
S 2002::/16 [1/0]
  via ::, Tunnel0
C 2002:AC10:1703:1::/64 [0/0]
  via ::, Tunnel0
L 2002:AC10:1703:1::3/128 [0/0]
  via ::, Tunnel0
L FE80::/10 [0/0]
  via ::, Null0
```

```
S   FEC0::1:0/112 [1/0]
    via 2002:AC10:C01:1::1
C   FEC0::3:0/112 [0/0]
    via ::, Loopback0
L   FEC0::3:1/128 [0/0]
    via ::, Loopback0
L   FF00::/8 [0/0]
    via ::, Null0
```

R1#ping FEC0::3:1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to FEC0::3:1, timeout is 2 seconds:

!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 64/67/68 ms

R3#ping FEC0::1:1

Type escape sequence to abort.

Sending 5, 100-byte ICMP Echos to FEC0::1:1, timeout is 2 seconds:

!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 64/66/68 ms