

Solarium Linux Masternode with Windows Cold Wallet

This is the condensed version of the video showing how to install and set up a Linux VPS with Windows cold wallet setup for a Solarium masternode. If you've never set up a masternode before, I suggest watching the video the first time. Subsequent setups you can just use these condensed walkthroughs.

I) Install Windows Cold wallet


1. Go to Solarium github site (<https://github.com/solariumcoin/wallet/blob/master/SolariumCore.zip>)
2. Click the download button
3. Once wallet is downloaded, install it to your desired location
4. Run the wallet and wait for it to sync
5. Create a masternode collateral address (I suggest to also create an address you can send coins to from your exchange so you don't have to send directly from exchange to your collateral address as it will be tricky to get the exact amount when sending from exchange directly to your collateral address)
6. Encrypt wallet (this will force a close of the wallet to finish encryption)
7. Run wallet again
8. Make a backup of wallet and store offline

II) Create collateral transaction

1. Send 10000 coins to your collateral address in one single transaction.


III) Install Putty and generate RSA key with PuttyGen

1. Go to Putty website (<https://www.putty.org/>)
2. Click the link for "download Putty here"
3. Click the appropriate link for your operating system
4. Install Putty
5. In the Putty programs directory, run PuttyGen




6. Click the "Generate" button and move mouse around until status bar fills up (see screenshot below for button location)
7. Enter a secure passphrase to encrypt your private key (see screenshot below for passphrase location)
8. Click "Save Public Key" button and save public key in an appropriate location (see screenshot below for button location)

- Click “Save Private Key” button and save private key in an appropriate location (see screenshot below for button location)
- Leave window open for use in later steps




IV) Set up VPS

- Go to vultr to set up an account (affiliate link: <https://www.vultr.com/?ref=7409995>)
- If first time using vultr, link a payment method and add some funds
- In the “Servers” tab, click the link for “SSH Keys”




- Enter a name for this key

- Copy the public key from PuttyGen window and paste into the key area




- Click "Add SSH Key" button and it should say it was added successfully
- Click the circled plus sign to deploy a new server




- In "Server Location" section, choose your continent and then a location closest to you
- In "Server Type" section, choose Ubuntu 16.04 x64
- In "Server Size" section, choose the \$5/month option (1024 MB memory)
- Scroll down to "SSH Keys" section and choose the RSA key you added in step IV.6 above
- In the "Enter Server Hostname" textbox, enter a name for this server (I named it My_MN01 for this example in screenshots below, but I would name it with the coin name you are creating a masternode for....like CoinName_MN01)
- Click "Deploy Now" button


14. Wait until status changes to “Running” and then click whitespace above the server IP address to see more details of the server



15. Open the Putty program




16. In the Putty Configuration window, expand the “Connection” heading
17. Expand the “SSH” heading, and click the “Auth” section (see screenshot below)
18. Click the “Browse” button and browse for the private key you created in step III.9 above




19. Scroll the left side back up to the top

20. Copy the IP address of your vultr server you just created and paste it into the “Host Name (or IP Address)” text box (see screenshot below)
21. Enter a name for this session in the “Saved Sessions” textbox (I suggest using the coin’s name in the for the name....something like Coiname_MN01) and click the “Save” button to save this configuration in case you need to “Load” it back up in the future



22. Click the “Open” button at bottom of window
23. Click “Yes” to allow the connection in the warning prompt that displays
24. In the SSH session, enter `root` when prompted to “login as”
25. When prompted for passphrase, enter the passphrase you used when creating the private key in step III.7 above
26. You will be logged in and it will be ready for commands (whenever the command prompt is given, it is ready and waiting for the next command)



Enter the following 2 commands one at a time. Copy and paste them one at a time into the Putty window. To paste in Putty, just right-click your mouse....it automatically will paste. Then hit the <Enter> key on your keyboard to run the command you pasted. Enter these one at a time and wait for the command prompt to return before entering the next...

(this first “wget” command is a single command but shows as 2 lines in the PDF. Copy the entire thing and run it as a single command)

```
wget -q https://raw.githubusercontent.com/Realbityoda/Solarium-
XLRG/master/solarium_install.sh
```

```
bash solarium_install.sh
```

27. After a few minutes, the window will prompt you to “enter your Solarium Masternode GEN Key”. Do not type anything, just hit <enter> on your keyboard to allow the Linux server to create a new key.
28. After another minute or 2, the screen will return to the command prompt. It will look like this...

```

root@quest: ~
Configuration file is: /root/.solarium/solarium.conf
Start: systemctl start Solarium.service
Stop: systemctl stop Solarium.service
VPS IP:PORT 108.61.157.207:5151
MASTERNODE GENKEY is: 7Sj1dKTLj1XbHbGE6ZPGdI95cheh873rBcmjJilvhBPVoEKYfW
Please check Solarium is running with the following command: systemctl status So
larium.service
Use solarium-cli masternode status to check your MN.
Sentinel is installed in /root/.solarium/sentinel
Sentinel logs is: /root/.solarium/sentinel.log

Follow twitter to stay updated. https://twitter.com/Real_Bit_Yoda

Donations accepted but never required.

BCH: qzgnck23pwfag8ucz2f0vf0j5kshtuql5hmmwjhds
ETH: 0x765eA1753A1eB7b12500499405e811f4d5164554
LTC: LNT9E9put2K8djTSZyR3jE72o7NMXNrb4aB

root@quest:~#

```


29. Your VPS “daemon” is now running. Minimize the Putty window, do not close it yet.

V) Configure the masternode in the windows cold wallet

1. Go back to your windows wallet and if your debug window is not open still, re-open it by going under the “Tools” menu, choose “Debug Console”
2. Go to the “Console” tab and type `masternode outputs` into the textbox at the bottom and hit the <Enter> key on the keyboard.
3. Leave the “Debug Console” open and go back under the “Tools” menu and choose “Open masternode configuration file”
4. In the configuration file enter the following information on a single line....


MN1 [VPS IP Address]:5151 [Masternode genkey value] [masternode outputs TxID value] [masternode outputs 1/0 value]

5. In the line you just pasted into the the config file, replace the [VPS IP Address] with your VPS server IP address found in the Putty window. To copy from the Putty, left-click and drag to highlight the text you want to copy and just release the mouse button. Do no right-click or use any commands. As soon as you release the mouse button, whatever is highlighted is automatically put into your clipboard. Then just go into your config file and paste as normal (either <CTRL>-V or right-click and choose paste).
6. Replace the [Masternode genkey value] with the value from the Putty window.




7. Replace the [masternode outputs TxID value] and [masternode outputs 1/0 value] with the 2 values you obtained by running the “masternode outputs” command in step V.2

above...



```
# Masternode config file
# Format: alias IP:port masternodeprivkey collateral_output_txid collateral_output_index
# Example: mn1 127.0.0.2:9333 93HaYBVUCYjEMeeH1Y4sBGLALQZE1Yc1K64xiqgX37tG8DL8Xg 2bcd3c84c84f87eaa86e4e56834c92927a07f9e18718810b92e0d0324456a67c 0
MN1 108.61.157.207:5151 7Sj1dKTLj1XbHbGE8ZPGdT95theh873rBcmjJiLvHBPVcEKYfvW 336bb9a5e1a1dba743b52c82b00b225b39a7e8b7cc4af0829f038e8fd1507be4 0
```

8. Your masternode config file should look like this....



```
# Masternode config file
# Format: alias IP:port masternodeprivkey collateral_output_txid collateral_output_index
# MN1 123.45.67.890:3300 7V7y8fgYpDDFCmg82TpDuN428ta4V7ku1b34myLufoopt2XvEVZ a2eF72eb896f676289250a844ebf265f0fba2eb038e318630476d3f==658a4ae 1
```

9. Under the “File” menu, choose “Save”
10. Under the “File’ menu, choose “Exit”
11. Back in the windows wallet, choose “File” -> “exit” to close the wallet
12. Re-start the wallet so it uses the config file you just edited
13. Wait for wallet to sync up completely
14. Go to the “Masternodes” tab in the wallet
15. Click the “Start Missing” button to start the masternode



16. The masternode should change status to “PRE-ENABLED”
17. Wait 10 minutes to an hour and it should change to “ENABLED”
18. Wait 1 hour to 12 hours (or possibly 24 hours) and you receive your first masternode reward