



MAGNET ROADS

Unity Package User Documentation


Written by Jonathan Langley

contact@tbinteractive.co.uk

www.tbinteractive.co.uk

Contents

Introducing Magnet Roads & Intersections	1
Magnet Roads.....	1
Adding Magnet Roads to Your Scene.....	1
Editing Magnet Roads	2
Getting Usable Information from Roads.....	3
Intersections	3
Adding Intersections to Your Scene	3
Intersection Start Points	3
Editing Intersections	3
Getting Usable Information from Intersections	4
[NEW IN v1.1] Editing Roads & Intersections at Runtime	4
[NEW IN v1.1] Saving & Loading From XML	4
Included Examples.....	5
Track Demo	5
Traversal Demo	5
[NEW IN v1.1] Runtime Demo.....	5



Magnet Roads

User Documentation

Introducing Magnet Roads & Intersections

Magnet roads is a simple to use alternative to some of the more complex road creation packages currently available on the Unity Store. Magnet roads allows you to quickly and efficiently create intricately connected road networks or racetracks with a simple to use polarised snapping system.

In short, each road has a **'Positive'** and a **'Negative'** end. These ends can be attached to the opposite polarity of any other magnet road in the scene (see fig. 1 for an example of the polar ends of the magnet roads). In addition to the magnetised road ends, there are also 'Bipolar' intersection points. These unique points only exist on the intersection road pieces. Bipolar snapping points will accept any end of a magnet road regardless of the point's polarity (See fig. 2); bipolar snap points appear as white circles.



Fig. 1 – Exemplar magnet road w/ polar ends




Fig. 2 – Intersection w/ bipolar points

Magnet Roads

Adding Magnet Roads to Your Scene

Once you've added the Magnet Roads package to your project, a **'Torchbearer Interactive'** menu will be added to your editor window under **'Tools'**. From this dropdown you can spawn new instances of both intersections and magnet roads. *Note: these new instances will always spawn at the root of the scene (0.0, 0.0, 0.0).* Intersections will generate instantly, whereas roads will only appear once selected in the editor. Once selected, the road will be represented by a curve with handles. The two handles at either end will manipulate the source points of the road, the two on the inside handle the curvature of the road. Once you are happy with the position and curvature of the road, simply press the orange **'Generate Road Mesh'** button in the road's inspector window. *Note: To snap-select an end, drag it into a magnet end and press **Generate***

You may edit and re-generate your magnet roads at any time after initial generation. For additional information on the tools available to edit existing roads, see the **'Editing Magnet Roads'** section.




Editing Magnet Roads

You will notice several editable fields in the inspector window when you are manipulating a road's spline. These fields are named and function as such:

FIELD NAME	VALUE TYPE - FUNCTION
surfaceMaterial	Material – The Material to apply to the road's surface
sideMaterial	Material – The Material to apply to the road's sides
roadWidth	Floating Point – The width of the road to be generated
slopeWidth	Floating Point – The distance from the edge of the road to the bottom of the sloped edge
stepsPerCurve	Integer – The number of points along the curve from which to extrapolate mesh vertex data (higher number = higher poly road)
showRoadOutline	Boolean – Toggles whether or not the outline of the road should be displayed in the editor before generation
showCarRoutes	Boolean – Toggles whether or not the left and right road lane routes are drawn onto the road
showRoadSides	Boolean – Toggles whether the outline of the road sides are drawn in editor before generation
sideDepth	Boolean – The distance between the road surface and the bottom/top of the road sides

Using these editable values you can achieve numerous road effects. Some examples:



E.g. High sided highway style road, road with sidewalk, downward sloped sides

In addition to the road's editable values, there are also some test buttons embedded into the inspector window. These extrapolate vertex data from the spline to produce a **Vector3** array; using this array the test method then sends a '**Road Follower**' to track this route in-editor – even allowing the user to select their own unique test vehicle GameObject (see fig. 3). For more information on the methods available to the user see the section called '**Getting Useable Information from Roads**'.




Fig. 3 – Road inspector's testing buttons, indicating the different lanes available to test (+add/remove curve buttons)



Getting Usable Information from Roads

This section will outline the various public methods the user can invoke in their own scripts to pull some of the pre-generated data out of the roads. *Note: this section will only cover public methods which offer some benefit to the developer, other functionality should be considered only useful to the magnet roads themselves.*

METHOD NAME	RETURN TYPE – FUNCTION
<code>GetMiddleCarPath()</code>	Vector3[] – Returns a vector array of points along the road’s curve based on the number of stepsPerCurve moving from the positive to the negative end of the road.
<code>GetLeftCarPath()</code>	Vector3[] – Similar to the previous method, however this one offsets the vector array to the left side of the road based on the roadWidth . Again, works from positive to negative.
<code>GetRightCarPath()</code>	Vector3[] – Essentially the inverse of the previous method: offset to the right, moves from negative to positive.
<code>GetClosestSnapPointFromVector()</code>	SnapPoint – This returns the closest snap point on the road to a user defined world space vector.

In addition to these methods, there is also an accessor for each of the road’s snap points. These are: **SnapNodeRight** and **SnapNodeLeft**; both of which return the **Transform** of their respective snap point.

Intersections

Adding Intersections to Your Scene

Like the roads before, to spawn a new intersection you simply click the ‘**Torchbearer Interactive**’ toolbar menu, and go to **Magnet Roads -> New Intersection**. Here you will have two options; a three and a four lane intersection. In terms of functionality, these intersections function exactly the same as one another; the major difference being the number of points at which Magnet Roads can connect.




Fig. 4 – Start Points visible as spheres

Intersection Start Points

A unique feature of the intersections is that they also generate a set of objects called **StartPoints**. These points indicate entrances to certain lanes on the road and are of potential use to developers looking to create traffic system for their roads (see the example scene: **TraversalDemo** to look at **StartPoints** in-use, also see Fig. 4).

Editing Intersections

Again, like the roads, intersections have some values in the inspector which you can manipulate – only, much more basic. These are as follows:

FIELD NAME	VALUE TYPE - FUNCTION
<code>surfaceMaterial</code>	Material – The Material to apply to the intersection’s surface
<code>sideMaterial</code>	Material – The Material to apply to the intersection’s sides
<code>roadWidth</code>	Floating Point – The width intersection to be generated (preferably identical to that of any connecting roads)
<code>sideDepth</code>	Floating Point – The size of the mesh generated on the sides of the intersection.
<code>slopeWidth</code>	Floating Point – The distance between the road’s edge and the sides



Getting Usable Information from Intersections

Unlike the roads, intersections do not have a great many methods to call in order to extrapolate information. Instead, roads simply hold references to the **SnapPoints** and **StartPoints** it possesses. These are acquired through the accessors: **SnapNodes** and **StartNodes** respectively.


Pressing the orange '**Regenerate Intersection Mesh**' will re-create any deleted start or snap points as well as update the intersection with any new **roadWidth** or **sideDepth** values.

[NEW IN v1.1] Editing Roads & Intersections at Runtime

As of version 1.1.0, real-time road editing has been implemented into Magnet Roads as a feature in of itself. This functionality provides users with access to some brand new methods.

METHOD NAME	VALUE TYPE - FUNCTION
CreateNewSplineRoad()	This method creates a new Magnet Road at the centre of the world (0.0, 0.0, 0.0).
CreateNewThreeLane()	This method creates a new three way intersection at the root of the world.
CreateNewFourLane()	This method creates a new four way intersection at the root of the world.
EnableRuntimeEditing()	This allows the user to manipulate the road at runtime.
DisableRuntimeEditing()	This prevents the user from being able to manipulate the road at runtime.
AddCurve()	New method for adding a curve to the road at runtime
RemoveCurve()	Removes a curve from the road at runtime

In addition to these methods, there is also an accessor used to return the roads editable state (Boolean) called **IsEditableAtRuntime**.



[NEW IN v1.1] Saving & Loading From XML

To save and load roads in the editor, simply make use of the 'Torchbearer Interactive' dropdown menu. You will see the saving and loading options under the 'Magnet Roads' subcategory. In addition to this you can save and load these roads at runtime with the following functions:

METHOD NAME	VALUE TYPE - FUNCTION
SaveRoadToXML(path)	Saves this Magnet Road to an .xml file, takes an optional path string as a parameter – leave blank for default save location.
SaveRoadsToXML(path)	Static method to save all current Magnet Roads & intersections in the scene to one .xml file. Optional path too.
LoadRoadsFromXML(path)	Loads and creates Magnet Roads and intersections from any suitable .xml files.



Included Examples

Track Demo

The track demo contains a small circuit created with Magnet Roads, download a suitable vehicle from the Asset Store and give it a try...

Traversal Demo

This demo relies on two scripts, separate from the Magnet Road tool. These are: **TravelNode.cs** and **RouteManager.cs**. The TravelNode script simply stores information about the roads connecting intersections and the relevant start points to those routes; the RouteManager script makes use of all these TravelNodes to divine viable routes between the intersections.

[NEW IN v1.1] Runtime Demo

This demo showcases the runtime editing features of Magnet Roads v1.1.0 – load the scene and enter play mode to see the runtime functionality in action.

